



User Guide

# Amazon Linux 2023



# Amazon Linux 2023: User Guide

Copyright © 2024 Amazon Web Services, Inc. and/or its affiliates. All rights reserved.

Amazon's trademarks and trade dress may not be used in connection with any product or service that is not Amazon's, in any manner that is likely to cause confusion among customers, or in any manner that disparages or discredits Amazon. All other trademarks not owned by Amazon are the property of their respective owners, who may or may not be affiliated with, connected to, or sponsored by Amazon.

---

# Table of Contents

<b>What is Amazon Linux 2023? .....</b>	<b>1</b>
Release cadence .....	1
Major and minor releases .....	3
Consuming new releases .....	4
Long-term support policy .....	4
Naming and versioning .....	4
Performance and operational optimizations .....	5
Relationship to Fedora .....	7
Customized cloud-init .....	7
Security updates and features .....	9
Manage updates .....	9
Security in the cloud .....	9
SELinux modes .....	9
Compliance program .....	10
SSH server default .....	10
Major features of OpenSSL 3 .....	10
Networking service .....	10
Core toolchain packages glibc, gcc, binutils .....	11
Package management tool .....	12
Default SSH server configuration .....	12
<b>Deprecated Functionality .....</b>	<b>15</b>
compat- packages .....	15
Deprecated functionality discontinued in AL1, removed in AL2 .....	15
32-bit x86 (i686) AMIs .....	16
aws-apitools-* replaced by AWS CLI .....	16
systemd replaces upstart in AL2 .....	17
Functionality deprecated in AL2 and removed in AL2023 .....	17
32-bit x86 (i686) Packages .....	18
aws-apitools-* replaced by AWS CLI .....	18
bzr revision control system .....	19
cgroup v1 .....	19
log4j hotpatch (log4j-cve-2021-44228-hotpatch) .....	19
lsb_release and the system-lsb-core package .....	20
mcrypt .....	20

OpenJDK 7 (java-1.7.0-openjdk) .....	21
Python 2.7 .....	21
rsyslog-openssl replaces rsyslog-gnutls .....	21
Network Information Service (NIS) / yp .....	21
Multiple domain names in Amazon VPC create-dhcp-options .....	21
<b>Deprecated in AL2023 .....</b>	<b>22</b>
32bit x86 (i686) runtime support .....	23
Berkeley DB (libdb) .....	23
cron .....	23
IMDSv1 .....	24
pcre version 1 .....	24
System V init (sysvinit) .....	24
<b>Comparing AL2 and AL2023 .....</b>	<b>25</b>
Added, upgraded, and removed packages .....	26
Support for each release .....	26
Naming and versioning changes .....	26
Optimizations .....	26
Sourced from multiple upstreams .....	27
Networking system service .....	27
Package manager .....	27
Using cloud-init .....	27
Graphical desktop support .....	28
Compiler Triplet .....	28
32bit x86 (i686) Packages .....	28
lsb_release and the system-lsb-core package .....	28
Extra Packages for Enterprise Linux (EPEL) .....	29
Python 2.7 has been replaced with Python 3 .....	29
Security updates .....	30
SELinux .....	30
OpenSSL 3 .....	30
IMDSv2 .....	31
Removal of log4j hotpatch (log4j-cve-2021-44228-hotpatch) .....	31
Deterministic upgrades for stability .....	32
gp3 as default Amazon EBS volume type .....	32
Unified Control Group hierarchy (cgroup v2) .....	32
systemd timers replace cron .....	33

Improved toolchain: gcc, binutils, and glibc .....	33
systemd journal replaces rsyslog .....	34
Minimized package dependencies .....	34
Package changes for curl and libcurl .....	34
GNU Privacy Guard (GNUPG) .....	35
Amazon Corretto as the default JVM .....	35
AWS CLI v2 .....	35
UEFI Preferred and Secure Boot .....	35
SSH server default configuration changes .....	35
Kernel changes in AL2023 from AL2 .....	36
IPv4 TTL .....	36
Security focused kernel config changes .....	36
Other kernel configuration changes .....	40
Kernel Filesystem support .....	42
AMI and Container Image changes .....	47
Amazon Linux 2 and AL2023 AMI comparison .....	47
Amazon Linux 2 and AL2023 Minimal AMI comparison .....	80
Amazon Linux 2 and AL2023 Container comparison .....	100
<b>Comparing AL1 and AL2023 .....</b>	<b>109</b>
Support for each release .....	109
systemd replaces upstart as init system .....	110
Python 2.6 and 2.7 has been replaced with Python 3 .....	110
OpenJDK 8 as oldest JDK .....	110
Kernel changes in AL2023 from AL1 .....	110
Kernel Live Patching .....	110
Kernel file system support .....	110
Security focused kernel config changes .....	112
Other kernel configuration changes .....	114
AL1 and AL2023 AMI comparison .....	115
AL1 and AL2023 Minimal AMI comparison .....	149
AL1 and AL2023 Container comparison .....	169
<b>System Requirements .....</b>	<b>178</b>
CPU requirements for running AL2023 .....	178
ARM CPU Requirements for AL2023 .....	178
x86-64 CPU Requirements for AL2023 .....	179
Memory (RAM) requirements for running AL2023 .....	179

<b>Using AL2023 on AWS .....</b>	<b>181</b>
Getting started with AWS .....	181
Sign up for an AWS account .....	181
Create a user with administrative access .....	182
Granting programmatic access .....	183
AL2023 on Amazon EC2 .....	185
Launching AL2023 using the Amazon EC2 console .....	185
Launching AL2023 using the SSM parameter and AWS CLI .....	186
Launching the latest AL2023 AMI using AWS CloudFormation .....	188
Launching AL2023 using a specific AMI ID .....	189
AL2023 AMI deprecation and life cycle .....	189
Connecting to AL2023 instances .....	190
Comparing AL2023 standard (default) and minimal AMIs .....	191
AL2023 in containers .....	218
AL2023 Base Container Image .....	219
AL2023 Minimal container image .....	221
Building bare-bones AL2023 container images .....	223
AL2023 container image package list comparison .....	227
AL2023 Minimal AMI compared to container images .....	233
AL2023 on Elastic Beanstalk .....	250
AL2023 CloudShell .....	250
AL2023 for Amazon ECS container hosts .....	251
Amazon ECS relevant changes since AL2 .....	251
Custom Amazon ECS-optimized AMI .....	252
Amazon EFS on AL2023 .....	252
amazon-efs-utils .....	253
Mounting Amazon EFS file system .....	253
Amazon EMR on AL2023 .....	253
AL2023 based Amazon EMR releases .....	253
AL2023 based Amazon EMR on EKS .....	254
AL2023 on AWS Lambda .....	254
provided.al2023 Lambda runtime .....	254
AL2023 based runtimes .....	254
<b>Tutorials .....</b>	<b>255</b>
Install LAMP on AL2023 .....	255
Step 1: Prepare the LAMP server .....	256

Step 2: Test your LAMP server .....	260
Step 3: Secure the database server .....	262
Step 4: (Optional) Install phpMyAdmin .....	263
Troubleshoot .....	266
Related topics .....	267
<b>Configure SSL/TLS on AL2023 .....</b>	<b>267</b>
Prerequisites .....	269
Step 1: Enable TLS on the server .....	270
Step 2: Obtain a CA-signed certificate .....	273
Step 3: Test and harden the security configuration .....	280
Troubleshoot .....	284
<b>Host a WordPress blog on AL2023 .....</b>	<b>285</b>
Prerequisites .....	286
Install WordPress .....	286
Next steps .....	296
Help! My public DNS name changed and now my blog is broken .....	298
<b>AL2023 outside Amazon EC2 .....</b>	<b>300</b>
Download AL2023 VM Images .....	300
Supported Configurations .....	300
KVM Requirements .....	301
VMware Requirements .....	303
Hyper-V Requirements .....	305
AL2023 VM configuration .....	307
NoCloud seed.iso based configuration .....	308
VMware guestinfo based configuration .....	312
AL2023 package list comparison for the standard AMI and KVM image .....	314
AL2023 package list comparison for the standard AMI and VMware OVA image .....	338
AL2023 package list comparison for the standard AMI and Hyper-V image .....	364
<b>Updating AL2023 .....</b>	<b>390</b>
Receive notifications on new updates .....	390
Managing updates .....	391
Checking for available package updates .....	391
Applying security updates using DNF and repository versions .....	393
Automatic service restart after (security) updates .....	396
Launching an instance with the latest repository version enabled .....	397
Getting package support information .....	398

Checking for newer repository versions .....	398
Adding, enabling, or disabling new repositories .....	401
Adding repositories with cloud-init .....	404
Using Deterministic upgrades through versioned repository on AL2023 .....	405
Control the updates received from major and minor releases .....	405
Differences between minor and major version upgrades .....	406
Control the package updates available from the AL2023 repositories .....	406
Deterministic upgrades through versioned repositories usage .....	406
Kernel Live Patching .....	412
Limitations .....	413
Supported configurations and prerequisites .....	413
Work with Kernel Live Patching .....	414
<b>Programming languages and runtimes .....</b>	<b>420</b>
C/C++ and Fortran .....	420
Go .....	421
AL2023 Lambda function: Go .....	422
Java .....	422
Perl .....	422
Perl modules .....	422
PHP .....	423
Migrating to new PHP versions .....	423
Migrating from PHP 7.x .....	423
PHP modules .....	424
Python .....	424
Python modules .....	425
Rust .....	425
AL2023 Lambda function: Rust .....	425
<b>Security and Compliance .....</b>	<b>426</b>
Security advisories .....	427
ALAS Announcements .....	427
ALAS FAQs .....	427
Setting SELinux modes for AL2023 .....	428
Default SELinux status and modes for AL2023 .....	428
Change to enforcing mode .....	429
Option to disable SELinux .....	430
Enable FIPS Mode on AL2023 .....	432

Kernel Hardening .....	433
Kernel Hardening options (architecture independent) .....	433
x86-64 specific Kernel Hardening options .....	446
aarch64 specific Kernel Hardening options .....	448
UEFI Secure Boot on AL2023 .....	450
Enable UEFI Secure Boot on AL2023 .....	450
Enrollment of an existing instance .....	451
Register image from snapshot .....	452
Revocation updates .....	452
How UEFI Secure Boot works on AL2023 .....	453
Enrolling your own keys .....	453

# What is Amazon Linux 2023?

Amazon Linux 2023 (AL2023) is the next generation of Amazon Linux from Amazon Web Services (AWS). With AL2023, you can develop and run cloud and enterprise applications in a secure, stable, and high-performance runtime environment. Also you get an application environment that offers long-term support with access to the latest innovations in Linux. AL2023 is provided at no additional charge.

AL2023 is the successor to Amazon Linux 2 (AL2). For information about the differences between AL2023 and AL2, see [Comparing AL2 and AL2023](#) and [Package changes in AL2023](#).

## Topics

- [Release cadence](#)
- [Naming and versioning](#)
- [Performance and operational optimizations](#)
- [Relationship to Fedora](#)
- [Customized cloud-init](#)
- [Security updates and features](#)
- [Networking service](#)
- [Core toolchain packages glibc, gcc, binutils](#)
- [Package management tool](#)
- [Default SSH server configuration](#)

## Release cadence

A new major version of Amazon Linux is released every two years and includes five years of support. Each release includes support in two phases. The standard support phase covers the first two years. Next, a maintenance phase continues support for an additional three years.

In the standard support phase, the release receives quarterly minor version updates. During the maintenance phase, a release receives only security updates and critical bug fixes that are published as soon as they're available.

Year	Amazon Linux 2023	Amazon Linux 2025	Amazon Linux 2027	Amazon Linux 2029
2023	 Standard support			
2024	 Standard support			
2025	Maintenance	 Standard support		
2026	Maintenance	 Standard support		
2027	Maintenance	Maintenance	 Standard support	
2028	 EOL	Maintenance	 Standard support	

Year	Amazon Linux 2023	Amazon Linux 2025	Amazon Linux 2027	Amazon Linux 2029
2029	 EOL	Maintenance	Maintenance	 Standard support
2030	 EOL	 EOL	Maintenance	 Standard support
2031	 EOL	 EOL	Maintenance	Maintenance

## Major and minor releases

With every Amazon Linux release (major version, minor version, or a security release), we release a new Linux Amazon Machine Image (AMI).

- **Major version release**— Includes new features and improvements in security and performance across the stack. The improvements might include major changes to the kernel, toolchain, Glib C, OpenSSL, and any other system libraries and utilities. Major releases of Amazon Linux are based in part on the current version of the upstream Fedora Linux distribution. AWS might add or replace specific packages from other non-Fedora upstreams.
- **Minor version release**— A quarterly update that includes security updates, bug fixes, and new features and packages. Each minor version is a cumulative list of updates that includes security and bug fixes in addition to new features and packages. These releases might include latest language runtimes, such as PHP. They might also include other popular software packages such as Ansible and Docker.

## Consuming new releases

Updates are provided through a combination of new Amazon Machine Image (AMI) releases and corresponding new repositories. By default, a new AMI and the repository that it points to are coupled. However, you can point your running Amazon EC2 instances to newer repository versions over time to apply updates on the running instances. You can also update by launching new instances of the latest AMIs.

## Long-term support policy

Amazon Linux provides updates for all of your packages and maintains compatibility within a major version for your applications that are built on Amazon Linux. Core packages such as the glibc library, OpenSSL, OpenSSH, and the DNF package manager receive support for the lifetime of the major AL2023 release. Packages that aren't part of the core packages are supported based on their specific upstream sources. You can see the specific support status and dates of individual packages by running the following command.

```
$ sudo dnf supportinfo --pkg packagename
```

You can get information on all currently installed packages by running the following command.

```
$ sudo dnf supportinfo --show installed
```

The full list of core packages is finalized during the preview. If you want to see more packages included as core packages, tell us. We evaluate as we are collecting feedback. Feedback on AL2023 can be provided through your designated AWS representative or by filing an issue in the [amazon-linux-2023 repo](#) on GitHub.

## Naming and versioning

AL2023 provides a minor release every three months during the two years of standard support. Each release is identified by an increment from 0 to N. 0 refers to the original major release for that iteration. All releases will be called Amazon Linux 2023. When Amazon Linux 2025 is released, AL2023 will enter extended support and receive updates for security updates and critical bug fixes.

For example, minor releases of AL2023 have the following format:

- 2023.0.20230301

- 2023.1.20230601
- 2023.2.20230901

The corresponding AL2023 AMIs have the following format:

- al2023-ami-2023.0.20230301.0-kernel-6.1-x86\_64
- al2023-ami-2023.1.20230601.0-kernel-6.1-x86\_64
- al2023-ami-2023.2.20230901.0-kernel-6.1-x86\_64

Within a specific minor version, regular AMI releases occur with a timestamp of the date of the AMI release.

- al2023-ami-2023.0.20230301.0-kernel-6.1-x86\_64
- al2023-ami-2023.0.20230410.0-kernel-6.1-x86\_64
- al2023-ami-2023.0.20230520.0-kernel-6.1-x86\_64

The recommended method for identifying an AL2 or AL2023 instance starts with reading the Common Platform Enumeration (CPE) string from `/etc/system-release-cpe`. Then, split the string into its fields. Finally, read the platform and version values.

AL2023 also introduces new files for platform identification:

- `/etc/amazon-linux-release` symlinks to `/etc/system-release`
- `/etc/amazon-linux-release-cpe` symlinks to `/etc/system-release-cpe`

These two files indicate that an instance is Amazon Linux. There's no need to read a file or split the string into fields, unless you want to know the specific platform and version values.

## Performance and operational optimizations

### Amazon Linux 6.1 kernel

- AL2023 uses the latest drivers for Elastic Network Adapter (ENA) and Elastic Fabric Adapter (EFA) devices. AL2023 focuses on performance and functionality backports for hardware in Amazon EC2 infrastructure.

- Kernel live patching is available for the x86\_64 and aarch64 instance types. This reduces the need for frequent reboots.
- All kernel build and runtime configurations include many of the same performance and operational optimizations of AL2.

## Base toolchain selection and default build flags

- AL2023 packages are built with compiler optimizations (-O2) enabled by default
- AL2023 packages are built requiring x86-64v2 for x86-64 systems (`-march=x86-64-v2`), and Graviton 2 or higher for aarch64 (`-march=armv8.2-a+crypto -mtune=neoverse-n1`).
- AL2023 packages are built with auto-vectorization enabled (`-ftree-vectorize`).
- AL2023 packages are built with Link Time Optimization (LTO) enabled.
- AL2023 uses the updated versions of Rust, Clang/LLVM, and Go.

## Package selection and versions

- Select backports to major system components include several performance improvements for running on Amazon EC2 infrastructure, especially Graviton instances.
- AL2023 is integrated with several AWS services and features. This includes the AWS CLI, SSM Agent, Amazon Kinesis Agent, and CloudFormation.
- AL2023 uses Amazon Corretto as the Java Development Kit (JDK).
- AL2023 provides database engines and programming language runtime updates to newer versions as they're released by upstream projects. Programming language runtimes with new versions are added when they're released.

## Deployment in a cloud environment

- The base AL2023 AMI and container images are frequently updated to support patching instance replacement.
- Kernel updates are included in AL2023 AMI updates. This means that you don't need to use commands such as `yum update` and `reboot` to update your kernel.
- In addition to the standard AL2023 AMI, a minimal AMI and container image is also available. Choose the minimal AMI to run an environment with the minimal number of packages that's required to run your service.

- By default, AL2023 AMIs and containers are locked to a specific version of the package repositories. There's no auto-update when they're launched. This means that you're always in control of when you ingest any package update. You can always test in a beta/gamma environment before rolling out to production. If there's a problem, you can use the pre-validated rollback path.

## Relationship to Fedora

AL2023 maintains its own release and support lifecycles independent of Fedora. AL2023 provides updated versions of open-source software, a larger variety of packages, and frequent releases. This preserves the familiar RPM-based operating systems.

The Generally Available (GA) version of AL2023 isn't directly comparable to any specific Fedora release. The AL2023 GA version includes components from Fedora 34, 35, and 36. Some of the components are the same as the components in Fedora and some are modified. Other components more closely resemble the components in CentOS 9 Streams or were developed independently. The Amazon Linux kernel is sourced from the long-term support options that are on kernel.org, chosen independently from Fedora.

## Customized cloud-init

The cloud-init package is an open-source application that bootstraps Linux images in a cloud computing environment. For more information, see [cloud-init Documentation](#).

AL2023 contains a customized version of cloud-init. With cloud-init, you can specify what occurs to your instance at boot time.

When you launch an instance, you can use the user-data fields to pass actions to cloud-init. This means that you can use common Amazon Machine Images (AMIs) for many use cases and configure them dynamically when you start an instance. AL2023 also uses cloud-init to configure the ec2-user account.

AL2023 uses the cloud-init actions in /etc/cloud/cloud.cfg.d and /etc/cloud/cloud.cfg. You can create your own cloud-init action files in the /etc/cloud/cloud.cfg.d directory. Cloud-init reads all the files in this directory in lexicographical order. Later files overwrite values in earlier files. When cloud-init launches an instance, the cloud-init package does the following configuration tasks:

- Sets the default locale
- Sets the hostname
- Parses and handles user-data
- Generates host private SSH keys
- Adds a user's public SSH keys to `.ssh/authorized_keys` for easy login and administration
- Prepares the repositories for package management
- Handles package actions that are defined in user-data
- Runs user scripts that are in user-data
- Mounts instance store volumes, if applicable
  - By default, if the `ephemeral0` instance store volume is present and contains a valid file system, the instance store volume is mounted at `/media/ephemeral0`. Otherwise, it's not mounted.
  - By default, for the `m1.small` and `c1.medium` instance types, all swap volumes that are associated with the instance are mounted.
  - You can override the default instance store volume mount with the following cloud-init directive:

```
#cloud-config
mounts:
- [ ephemeral0 ]
```

For more control over mounts, see [Mounts](#) in the cloud-init documentation.

- When an instance launches, instance store volumes that support TRIM aren't formatted. Before you can mount instance store volumes, you must partition and format instance store volumes.

For more information, see [Instance store volume TRIM support](#) in the *Amazon EC2 User Guide*.

- When you launch your instances, you can use the `disk_setup` module to partition and format your instance store volumes.

For more information, see [Disk Setup](#) in the cloud-init documentation.

For information about using cloud-init with SELinux, see [Use cloud-init to enable enforcing mode](#).

For information about cloud-init user-data formats, see [User-Data Formats](#) in the cloud-init documentation.

## Security updates and features

AL2023 provides many security updates and solutions.

### Topics

- [Manage updates](#)
- [Security in the cloud](#)
- [SELinux modes](#)
- [Compliance program](#)
- [SSH server default](#)
- [Major features of OpenSSL 3](#)

## Manage updates

Apply security updates using DNF and repository versions. For more information, see [Manage package and operating system updates in AL2023](#).

## Security in the cloud

Security is a shared responsibility between AWS and you. The [shared responsibility model](#) describes this as security of the cloud and security in the cloud. For more information, see [Security and Compliance in Amazon Linux 2023](#).

## SELinux modes

By default, SELinux is enabled and set to permissive mode in AL2023. In permissive mode, permission denials are logged but not enforced.

The SELinux policies define permissions for users, processes, programs, files, and devices. With SELinux, you can choose one of two policies. The policies are targeted or multi-level security (MLS).

For more information about SELinux modes and policy, see [Setting SELinux modes for AL2023](#) and [the SELinux Project Wiki](#).

## Compliance program

Independent auditors assess the security and compliance of AL2023 along with many AWS compliance programs.

## SSH server default

AL2023 includes OpenSSH 8.7. OpenSSH 8.7 by default disables the `ssh-rsa` key exchange algorithm. For more information, see [Default SSH server configuration](#).

## Major features of OpenSSL 3

- The Certificate Management Protocol (CMP, RFC 4210) includes both CRMF (RFC 4211) and HTTP transfer (RFC 6712).
- A HTTP or HTTPS client in `libcrypto` supports GET and POST actions, redirection, plain and ASN.1-encoded content, proxies, and timeouts.
- The EVP\_KDF works with Key Derivation Functions.
- The EVP\_MAC API works with MACs.
- Linux Kernel TLS support.

For more information, see the [OpenSSL migration guide](#).

## Networking service

The open-source project `systemd-networkd` is widely available in modern Linux distributions. The project uses a declarative configuration language that's similar to the rest of the `systemd` framework. Its primary configuration file types are `.network` and `.link` files.

The `amazon-ec2-net-utils` package generates interface-specific configurations in the `/run/systemd/network` directory. These configurations enable both IPv4 and IPv6 networking on interfaces when they're attached to an instance. These configurations also install policy routing rules that help ensure that locally sourced traffic is routed to the network through the corresponding instance's network interface. These rules ensure that the right traffic is routed through the Elastic Network Interface (ENI) from the associated addresses or prefixes. For more information about using ENI, see [Using ENI](#) in the *Amazon EC2 User Guide*.

You can customize this networking behavior by placing a custom configuration file in the `/etc/systemd/network` directory to override the default configuration settings contained in `/run/systemd/network`.

The [systemd.network](#) documentation describes how the `systemd-networkd` service determines the configuration that applies to a specific interface. It also generates alternative names, known as altnames, for the ENI-backed interfaces to reflect the properties of various AWS resources. These ENI-backed interface properties are the ENI ID and the DeviceIndex field of the ENI attachment. You can refer to these interfaces using their properties when using various tools, such as the `ip` command.

AL2023 instance interface names are generated using the systemd slot naming scheme. For more information, see [systemd.net naming scheme](#).

Additionally, AL2023 uses the `fq_codel` active queue management network transmission scheduling algorithm by default. For more information, see [CoDel overview](#).

## Core toolchain packages glibc, gcc, binutils

A subset of packages in Amazon Linux is designated as core toolchain packages. As a major part of AL2023, core packages receive five years of support. We might change the version of a package, but long-term support applies to the package included in the Amazon Linux release.

These three core packages provide a system toolchain that's used to build most software in the Amazon Linux distribution.

Package	Definition	Purpose
glibc 2.34	System C library	Used by most binary programs that provide standard functions and by the interface between programs and the kernel.
gcc 11.2	gcc compiler suite	Compiles C, C++, Fortran.
binutils 2.35	Assembler and linker plus other binary tools	Manipulates or inspects binary programs.

We recommend that updates to any glibc libraries are followed by a reboot. For updates to packages that control services, it might be sufficient to restart the services to pick up the updates. However, a system reboot ensures that all previous package and library updates are complete.

## Package management tool

The default software package management tool in AL2023 is DNF. DNF is the successor to YUM, the package management tool in AL2.

DNF is similar to YUM in its usage. Many DNF commands and command options are the same as YUM commands. In a Command Line Interface (CLI) command, in most cases `dnf` replaces `yum`.

For example, for the following AL2 yum commands:

```
$ sudo yum install packagename  
$ sudo yum search packagename  
$ sudo yum remove packagename
```

In AL2023, they become the following commands:

```
$ sudo dnf install packagename  
$ sudo dnf search packagename  
$ sudo dnf remove packagename
```

In AL2023 the `yum` command is still available, but as a pointer to the `dnf` command. So, when the `yum` command is used in the shell or in a script, all commands and options are the same as the DNF CLI. For more information about the differences between the YUM CLI and the DNF CLI, see [Changes in DNF CLI compared to YUM](#).

For a complete reference of commands and options for the `dnf` command, refer to the man page `man dnf`. For more information, see [DNF Command Reference](#).

## Default SSH server configuration

If you have SSH clients from several years ago, you might see an error when you connect to an instance. If the error tells you there's no matching host key type found, update your SSH host key to troubleshoot this issue.

### Default disabling of `ssh-rsa` signatures

AL2023 includes a default configuration that disables the legacy `ssh-rsa` host key algorithm and generates a reduced set of host keys. Clients must support the `ssh-ed25519` or the `ecdsa-sha2-nistp256` host key algorithm.

The default configuration accepts any of these key exchange algorithms:

- `curve25519-sha256`
- `curve25519-sha256@libssh.org`
- `ecdh-sha2-nistp256`
- `ecdh-sha2-nistp384`
- `ecdh-sha2-nistp521`
- `diffie-hellman-group-exchange-sha256`
- `diffie-hellman-group14-sha256`
- `diffie-hellman-group16-sha512`
- `diffie-hellman-group18-sha512`

By default, AL2023 generates `ed25519` and `ECDSA` host keys. Clients support either the `ssh-ed25519` or the `ecdsa-sha2-nistp256` host key algorithm. When you connect by SSH to an instance, you must use a client that supports a compatible algorithm, such as `ssh-ed25519` or `ecdsa-sha2-nistp256`. If you need to use other key types, override the list of generated keys with a `cloud-config` fragment in `user-data`.

In the following example, `cloud-config` generates a `rsa` host key with the `ecdsa` and `ed25519` keys.

```
#cloud-config
  ssh_genkeytypes:
    - ed25519
    - ecdsa
    - rsa
```

If you use an RSA key pair for public key authentication, your SSH client must support a `rsa-sha2-256` or `rsa-sha2-512` signature. If you're using an incompatible client and can't upgrade, re-enable `ssh-rsa` support on your instance. To re-enable `ssh-rsa` support, activate the LEGACY system crypto policy using the following commands.

```
$ sudo dnf install crypto-policies-scripts
```

```
$ sudo update-crypto-policies --set LEGACY
```

For more information about managing host keys, see [Amazon Linux Host keys](#).

# Deprecated Functionality in AL2023

Functionality deprecated in AL2 and not present in AL2023 is documented here. This is functionality such as features and packages that are present in AL2, but not in AL2023 and will not be added to AL2023. For more information about how long the functionality is supported in AL2, see [Deprecated functionality in AL2](#).

There is also functionality in AL2023 which is deprecated, and will be removed in a future release. This chapter describes what that functionality is, when it no longer supported, and when it will be removed from Amazon Linux. Understanding the deprecated functionality will help you deploy AL2023 as well as prepare for the next major version of Amazon Linux.

## Topics

- [compat- packages](#)
- [Deprecated functionality discontinued in AL1, removed in AL2](#)
- [Functionality deprecated in AL2 and removed in AL2023](#)
- [Deprecated in AL2023](#)

## compat- packages

Any packages in AL2 with the prefix of compat- are provided for binary compatibility with older binaries that have not yet been rebuilt for modern versions of the package. Each new major version of Amazon Linux will not carry forward any compat- package from prior releases.

All compat- packages in a release of Amazon Linux (e.g. AL2) are deprecated, and not present in the subsequent version (e.g. AL2023). We strongly recommend that software is rebuilt against updated versions of the libraries.

## Deprecated functionality discontinued in AL1, removed in AL2

This section describes functionality that is available in AL1, and is no longer available in AL2.

**Note**

As part of the maintenance support phase of AL1, some packages had an end-of-life (EOL) date earlier than the EOL of AL1. For more information, see [AL1 Package support statements](#).

**Note**

Some AL1 functionality was discontinued in earlier releases. For information, see the [AL1 Release Notes](#).

**Topics**

- [32-bit x86 \(i686\) AMIs](#)
- [aws-apitools-\\* replaced by AWS CLI](#)
- [systemd replaces upstart in AL2](#)

## 32-bit x86 (i686) AMIs

As part of the [2014.09 release of AL1](#), Amazon Linux announced that it would be the last release to produce 32-bit AMIs. Therefore, starting from the [2015.03 release of AL1](#), Amazon Linux no longer supports running the system in 32-bit mode. AL2 offers limited runtime support for 32-bit binaries on x86-64 hosts and does not provide development packages to enable the building of new 32-bit binaries. AL2023 no longer includes any 32-bit user space packages. We recommend that users complete their transition to 64-bit code before migrating to AL2023.

If you need to run 32-bit binaries on AL2023, it is possible to use the 32-bit userspace from AL2 inside an AL2 container running on top of AL2023.

## aws-apitools-\* replaced by AWS CLI

Before the release of the AWS CLI in September 2013, AWS made a set of command line utilities available, implemented in Java, which allowed users to make Amazon EC2 API calls. These tools were discontinued in 2015, with the AWS CLI becoming the preferred way to interact with Amazon EC2 APIs from the command line. The set of command line utilities includes the following aws-apitools-\* packages.

- aws-apitools-as
- aws-apitools-cfn
- aws-apitools-common
- aws-apitools-ec2
- aws-apitools-elb
- aws-apitools-mon

Upstream support for the aws-apitools-\* packages ended in March of 2017. Despite the lack of upstream support, Amazon Linux continued to ship some of these command line utilities, such as aws-apitools-ec2, to provide backward compatibility for users. The AWS CLI is a more robust and complete tool than the aws-apitools-\* packages as it is actively maintained and provides a means of using all AWS APIs.

The aws-apitools-\* packages were deprecated in March 2017 and will not be receiving further updates. All users of any of these packages should migrate to the AWS CLI as soon as possible. These packages are not present in AL2023.

AL1 also provided the aws-apitools-iam and aws-apitools-rds packages, which were deprecated in AL1, and are not present in Amazon Linux from AL2 onward.

## **systemd replaces upstart in AL2**

AL2 was the first Amazon Linux release to use the systemd init system, replacing upstart in AL1. Any upstart specific configuration must be changed as part of the migration from AL1 to a newer version of Amazon Linux. It is not possible to use systemd on AL1, so moving from upstart to systemd can only be done as part of moving to a more recent major version of Amazon Linux such as AL2 or AL2023.

## **Functionality deprecated in AL2 and removed in AL2023**

This section describes functionality that is available in AL2, and no longer available in AL2023.

### **Topics**

- [32-bit x86 \(i686\) Packages](#)
- [aws-apitools-\\* replaced by AWS CLI](#)
- [bzr revision control system](#)

- [cgroup v1](#)
- [log4j hotpatch \(log4j-cve-2021-44228-hotpatch\)](#)
- [lsb\\_release and the system LSB-core package](#)
- [mcrypt](#)
- [OpenJDK 7 \(java-1.7.0-openjdk\)](#)
- [Python 2.7](#)
- [rsyslog-openssl replaces rsyslog-gnutls](#)
- [Network Information Service \(NIS\) / yp](#)
- [Multiple domain names in Amazon VPC create-dhcp-options](#)

## 32-bit x86 (i686) Packages

As part of the [2014.09 release of AL1](#), we announced that it would be the last release to produce 32-bit AMIs. Therefore, starting from the [2015.03 release of AL1](#), Amazon Linux no longer supports running the system in 32-bit mode. AL2 provides limited runtime support for 32-bit binaries on x86-64 hosts and doesn't provide development packages to enable the building of new 32-bit binaries. AL2023 no longer includes any 32-bit userspace packages. We recommend customers complete their transition to 64-bit code.

If you need to run 32-bit binaries on AL2023, it is possible to use the 32-bit userspace from AL2 inside an AL2 container running on top of AL2023.

## **aws-apitools-\* replaced by AWS CLI**

Prior to release of the AWS CLI in September 2013, AWS made a set of command line utilities available, implemented in Java, which allowed customers to make Amazon EC2 API calls. These tools were deprecated in 2015, with the AWS CLI becoming the preferred way to interact with Amazon EC2 APIs from the command line. This includes the following `aws-apitools-*` packages.

- `aws-apitools-as`
- `aws-apitools-cfn`
- `aws-apitools-common`
- `aws-apitools-ec2`
- `aws-apitools-elb`
- `aws-apitools-mon`

Upstream support for the aws-apitools-\* packages ended in March of 2017. Despite the lack of upstream support, Amazon Linux continued to ship some of these command line utilities (such as aws-apitools-ec2) in order to provide backwards compatibility for customers. The AWS CLI is a more robust and complete tool than the aws-apitools-\* packages as it is actively maintained and provides a means of using all AWS APIs.

The aws-apitools-\* packages were deprecated in March 2017 and will not be receiving further updates. All users of any of these packages should migrate to the AWS CLI as soon as possible. These packages are not present in AL2023.

## bzr revision control system

The [GNU Bazaar](#) (bzr) revision control system is discontinued in AL2 and no longer present in AL2023.

Users of bzr are advised to migrate their repositories to git.

## cgroup v1

AL2023 moves to Unified Control Group hierarchy (cgroup v2), whereas AL2 uses cgroup v1. As AL2 doesn't support cgroup v2, this migration needs to be completed as part of moving to AL2023.

## log4j hotpatch ([log4j-cve-2021-44228-hotpatch](#))

### Note

The log4j-cve-2021-44228-hotpatch package is deprecated in AL2 and removed in AL2023.

In response to [CVE-2021-44228](#), Amazon Linux released an RPM packaged version of the [Hotpatch for Apache Log4j](#) for AL1 and AL2. In the [announcement of the addition of the hotpatch to Amazon Linux](#), we noted that "Installing the hotpatch is not a replacement for updating to a log4j version that mitigates CVE-2021-44228 or CVE-2021-45046.".

The hotpatch was a mitigation to allow time to patch log4j. The first general availability release of AL2023 was 15 months after [CVE-2021-44228](#), so AL2023 doesn't ship with the hotpatch (enabled or not).

Customers running their own log4j versions on Amazon Linux are advised to ensure they have updated to versions not affected by [CVE-2021-44228](#) or [CVE-2021-45046](#).

## **lsb\_release and the system-lsb-core package**

Historically, some software invoked the lsb\_release command (provided in AL2 by the system-lsb-core package) to get information about the Linux distribution that it was being run on. The Linux Standards Base (LSB) introduced this command and Linux distributions adopted it. Linux distributions have evolved to use the simpler standard of holding this information in /etc/os-release and other related files.

The os-release standard comes out of systemd. For more information, see [systemd os-release documentation](#).

AL2023 doesn't ship with the lsb\_release command, and doesn't include the system-lsb-core package. Software should complete the transition to the os-release standard to maintain compatibility with Amazon Linux and other major Linux distributions.

## **mcrypt**

The mcrypt library and associated PHP extension was deprecated in AL2, and is no longer present in AL2023.

Upstream PHP [deprecated the mcrypt extension in PHP 7.1](#) which was first released in December 2016 and had its final release in October 2019.

The upstream mcrypt library [last made a release in 2007](#), and has not made the migration from cvs revision control that [SourceForge required for new commits in 2017](#), with the most recent commit (and only for 3 years prior) being from 2011 removing the mention of the project having a maintainer.

Any remaining users of mcrypt are advised to port their code to OpenSSL, as mcrypt will not be added to AL2023.

## OpenJDK 7 (java-1.7.0-openjdk)

### Note

AL2023 provides several versions of [Amazon Corretto](#) to support Java based workloads.

The OpenJDK 7 packages are deprecated in AL2, and no longer present in AL2023. The oldest JDK available in AL2023 is provided by Corretto 8.

For more information about Java on Amazon Linux, see [Java in AL2023](#).

## Python 2.7

### Note

AL2023 removed Python 2.7, so any OS components requiring Python are written to work with Python 3. To continue to use a version of Python provided by and supported by Amazon Linux, convert Python 2 code to Python 3.

For more information about Python on Amazon Linux, see [Python in AL2023](#).

## **rsyslog-openssl replaces rsyslog-gnutls**

The `rsyslog-gnutls` package is deprecated in AL2, and no longer present in AL2023. The `rsyslog-openssl` package should be a drop-in replacement for any usage of the `rsyslog-gnutls` package.

## Network Information Service (NIS) / yp

The Network Information Service (NIS), originally called Yellow Pages or YP is deprecated in AL2, and no longer present in AL2023. This includes the following packages: `ypbind`, `ypserv`, and `yp-tools`. Other packages that integrate with NIS have this functionality removed in AL2023.

## Multiple domain names in Amazon VPC `create-dhcp-options`

In Amazon Linux 2, it was possible to pass multiple domain names in the `domain-name` parameter to [`create-dhcp-options`](#), which would result in `/etc/resolv.conf` containing something like `search foo.example.com bar.example.com`. The Amazon VPC DHCP server sends the list

of provided domain names using DHCP option 15, which only supports a single domain name (see [RFC 2132 section 3.17](#)). Since AL2023 uses `systemd-networkd` for network configuration, which follows the RFC, this accidental feature in AL2 is not present on AL2023

The [AWS CLI](#) and [Amazon VPC documentation](#) has this to say: "Some Linux operating systems accept multiple domain names separated by spaces. However, Windows and other Linux operating systems treat the value as a single domain, which results in unexpected behavior. If your DHCP option set is associated with a Amazon VPC that has instances running operating systems that treat the value as a single domain, specify only one domain name. "

On these systems, such as AL2023, specifying two domains using DHCP option 15 (which only allows one), and since the [space character is invalid in domain names](#), this will result in the space character being encoded as 032, resulting in `/etc/resolv.conf` containing search `foo.example.com032bar.example.com`.

In order to support multiple domain names, a DHCP server should use DHCP Option 119 (see [RFC 3397, section 2](#)). See the [Amazon VPC User Guide](#) for when this is supported by the Amazon VPC DHCP server.

## Deprecated in AL2023

This section describes functionality that exists in AL2023 and is likely to be removed in a future version of Amazon Linux. Each section will describe what the functionality is and when it is expected to removed from Amazon Linux.

### Note

This section will be updated over time as the Linux ecosystem evolves and future major versions of Amazon Linux are closer to release.

## Topics

- [32bit x86 \(i686\) runtime support](#)
- [Berkeley DB \(libdb\)](#)
- [cron](#)
- [IMDSv1](#)
- [pcre version 1](#)

- [System V init \(sysvinit\)](#)

## 32bit x86 (i686) runtime support

AL2023 retains the ability to run 32bit x86 (i686) binaries. It is likely that the next major version of Amazon Linux will no longer support running 32bit user space binaries.

## Berkeley DB (libdb)

AL2023 ships with version 5.3.28 of the Berkeley DB (libdb) library. This is the last version of Berkeley DB before the license changed to the GNU Affero GPLv3 (AGPL) license, from the less restrictive Sleepycat license.

There are few packages in AL2023 that remain reliant on Berkeley DB (libdb), and the library will be removed in the next major release of Amazon Linux.

### Note

The dnf package manager in AL2023 retains read-only support for a Berkeley DB (BDB) format rpm database. This support will be removed in the next major release of Amazon Linux.

## cron

The cronie package was installed by default on the AL2 AMI, providing support for the traditional crontab way of scheduling periodic tasks. In AL2023, cronie is not included by default. Therefore, support for crontab is no longer provided by default.

In AL2023, you can optionally install the cronie package to use classic cron jobs. We recommend that you migrate to systemd timers due to the added functionality provided by systemd.

It is possible that a future version of Amazon Linux, possibly the next major version, will no longer include support for classic cron jobs and complete the transition to systemd timers. We recommend that you migrate away from using cron.

## IMDSv1

By default, AL2023 AMIs are configured to launch in IMDSv2-only mode, disabling the use of IMDSv1. There is still the option to use AL2023 with IMDSv1 enabled. A future version of Amazon Linux is likely to enforce IMDSv2-only.

For more information on IMDS configuration for AMIs, see [Configure the AMI](#) in the *Amazon EC2 User Guide*.

## pcre version 1

The legacy `pcre` package is deprecated and will be removed in the next major release of Amazon Linux. The `pcre2` package is the successor. Although the first versions of AL2023 shipped with a limited number of packages building against `pcre`, these packages will be migrated to `pcre2` within AL2023. The deprecated `pcre` library will remain available in AL2023.

### Note

The deprecated version of `pcre` will not receive security updates for the full lifetime of AL2023. For more information about the `pcre` support lifecycle and the amount of time that the package will receive security updates, see the [package support statements on the pcre package](#).

## System V init (sysvinit)

Although AL2023 retains backwards compatibility with System V service (init) scripts, the upstream `systemd` project, as part of its [v254 release](#), announced the [deprecation of support for System V service scripts](#), and indicated that support will be removed in a future version of `systemd`. For more information, see [systemd](#).

AL2023 will retain backwards compatibility with System V service (init) scripts, but users are encouraged to migrate to using native `systemd` unit files in order to be prepared for when support for System V service (init) scripts is removed from Amazon Linux, likely in the next major release.

# Comparing AL2 and AL2023

The following topics describe key differences between AL2 and AL2023.

For more information on functionality deprecated in AL1, AL2, and AL2023, see [Deprecated Functionality in AL2023](#).

## Topics

- [Added, upgraded, and removed packages](#)
- [Support for each release](#)
- [Naming and versioning changes](#)
- [Optimizations](#)
- [Sourced from multiple upstreams](#)
- [Networking system service](#)
- [Package manager](#)
- [Using cloud-init](#)
- [Graphical desktop support](#)
- [Compiler Triplet](#)
- [32bit x86 \(i686\) Packages](#)
- [lsb\\_release and the system-lsb-core package](#)
- [Extra Packages for Enterprise Linux \(EPEL\)](#)
- [Python 2.7 has been replaced with Python 3](#)
- [Security updates](#)
- [Deterministic upgrades for stability](#)
- [gp3 as default Amazon EBS volume type](#)
- [Unified Control Group hierarchy \(cgroup v2\)](#)
- [systemd timers replace cron](#)
- [Improved toolchain: gcc, binutils, and glibc](#)
- [systemd journal replaces rsyslog](#)
- [Minimized package dependencies](#)
- [Amazon Corretto as the default JVM](#)
- [AWS CLI v2](#)

- [UEFI Preferred and Secure Boot](#)
- [SSH server default configuration changes](#)
- [AL2023 kernel changes from AL2](#)
- [AMI and Container Image changes](#)
- [Comparing packages installed on Amazon Linux 2 and Amazon Linux 2023 AMIs](#)
- [Comparing packages installed on Amazon Linux 2 and Amazon Linux 2023 Minimal AMIs](#)
- [Comparing packages installed on Amazon Linux 2 and Amazon Linux 2023 base container images](#)

## Added, upgraded, and removed packages

AL2023 contains thousands of software packages available for use. For a full list of all packages added, upgraded, or removed in AL2023 when compared to prior Amazon Linux versions, see [Package changes in AL2023](#).

To request a package to be added or changed in AL2023, file an issue in the [amazon-linux-2023 repo](#) on GitHub.

## Support for each release

For AL2023, we offer five years of support.

For more information, see [Release cadence](#).

## Naming and versioning changes

AL2023 supports the same mechanisms that AL2 supports for platform identification. AL2023 also introduces new files for platform identification.

For more information, see [Naming and versioning](#).

## Optimizations

AL2023 optimizes boot time to reduce the time from instance launch to running the customer workload. These optimizations span the Amazon EC2 instance kernel configuration, cloud-init configurations, and features that are built into packages in the OS such as mod and systemd.

For more information about optimizations, see [Performance and operational optimizations](#).

## Sourced from multiple upstreams

AL2023 is RPM-based and includes components sourced from multiple versions of Fedora and other distributions, such as CentOS 9 Stream. The Amazon Linux kernel is sourced from the long-term support (LTS) releases directly from kernel.org, chosen independently from other distributions.

For more information, see [Relationship to Fedora](#).

## Networking system service

The `systemd-networkd` system service manages the network interfaces in AL2023. This is a change from AL2, which uses ISC dhclient or dhclient.

For more information, see [Networking service](#).

## Package manager

The default software package management tool on AL2023 is DNF. DNF is the successor to YUM, the package management tool in AL2.

For more information, see [Package management tool](#).

## Using cloud-init

In AL2023, cloud-init manages the package repository. By default, in earlier versions of Amazon Linux, cloud-init installed security updates. This isn't the default for AL2023. The new deterministic upgrading features for updating `releasever` at launch describe the AL2023 way to enable package updates at launch. For more information, see [Manage package and operating system updates in AL2023](#) and [Deterministic upgrades for stability](#).

With AL2023, you can use cloud-init with SELinux. For more information, see [Use cloud-init to enable enforcing mode](#).

Cloud-init loads configuration content with cloud-init from remote locations using HTTP(S). In earlier versions, Amazon Linux doesn't alert you when remote resources are unavailable. In AL2023,

unavailable remote resources creates a fatal error and fails the cloud-init execution. This change in behavior from AL2, provides a safer "fail closed" default behavior.

For more information, see [Customized cloud-init](#) and the [cloud-init Documentation](#).

## Graphical desktop support

AL2023 is cloud-centered and optimized for Amazon EC2 usage and currently does not include a graphical or desktop environment. To provide feedback on GitHub, see <https://github.com/>.

## Compiler Triplet

AL2023 sets the compiler triplet for GCC and LLVM to indicate that amazon is the vendor.

Thus, the AL2 aarch64-redhat-linux-gcc becomes aarch64-amazon-linux-gcc on AL2023.

This should be completely transparent for most users, and might only affect those who are building compilers on AL2023.

## 32bit x86 (i686) Packages

As part of the [2014.09 release of AL1](#) it was announced that it would be the last release to produce 32-bit AMIs. Thus, from the [2015.03 release of AL1](#), Amazon Linux no longer supported running the system in 32-bit mode. AL2 offered limited runtime support for 32bit binaries on x86-64 hosts, and did not provide development packages to enable the building of new 32-bit binaries. AL2023 no longer includes any 32bit userspace packages. We recommend that you complete your transition to 64-bit code.

If you need to run 32-bit binaries on AL2023, it is possible to use the 32-bit user-space from AL2 inside an AL2 container running on top of AL2023.

## **lsb\_release and the system-lsb-core package**

Historically, some software invoked the lsb\_release command (provided in AL2 by the system-lsb-core package) to get information about the Linux distribution that it was being run on. The

Linux Standards Base (LSB) introduced this command and Linux distributions adopted it. Linux distributions have evolved to use the simpler standard of holding this information in /etc/os-release and other related files.

The os-release standard comes out of systemd. For more information, see [systemd os-release documentation](#).

AL2023 doesn't ship with the lsb\_release command, and doesn't include the system-lsb-core package. Software should complete the transition to the os-release standard to maintain compatibility with Amazon Linux and other major Linux distributions.

## Extra Packages for Enterprise Linux (EPEL)

Extra Packages for Enterprise Linux (EPEL) is a project in the Fedora community with the objective of creating a large array of packages for enterprise-level Linux operating systems. The project has primarily produced RHEL and CentOS packages. AL2 features a high level of compatibility with CentOS 7. As a result, many EPEL7 packages work on AL2. However, AL2023 doesn't support EPEL or EPEL-like repositories.

## Python 2.7 has been replaced with Python 3

AL2 provides support and security patches for Python 2.7 until June 2025, as part of our long-term support (LTS) commitment for AL2 core packages. This support extends beyond the upstream Python community declaration of Python 2.7 end-of-life of January 2020.

AL2 uses the yum package manager, which has a hard dependency on Python 2.7. In AL2023 the dnf package manager has migrated to Python 3, and no longer requires Python 2.7. AL2023 has completely moved to Python 3.

### Note

AL2023 removed Python 2.7, so any OS components requiring Python are written to work with Python 3. To continue to use a version of Python provided by and supported by Amazon Linux, convert Python 2 code to Python 3.

For more information on Python on Amazon Linux, see [Python in AL2023](#).

# Security updates

Amazon Linux 2023 improves upon the hardening present in AL2. For more information, see [Security and Compliance in Amazon Linux 2023](#). For more information on kernel hardening changes from AL2, see [Security focused kernel config changes](#).

## Topics

- [SELinux](#)
- [OpenSSL 3](#)
- [IMDSv2](#)
- [Removal of log4j hotpatch \(log4j-cve-2021-44228-hotpatch\)](#)

## SELinux

By default, Security Enhanced Linux (SELinux) for AL2023 is enabled and set to permissive mode. In permissive mode, permission denials are logged but not enforced.

SELinux is a security feature of the Amazon Linux kernel, which was disabled in AL2. SELinux is a collection of kernel features and utilities that provides mandatory access control (MAC) architecture into the major subsystems of the kernel.

For more information, see [Setting SELinux modes for AL2023](#).

For more information about SELinux repositories, tools, and policies, see [SELinux Notebook](#), [Types of SELinux policy](#), and [SELinux Project](#).

## OpenSSL 3

AL2023 features the Open Secure Sockets Layer version 3 (OpenSSL 3) cryptography toolkit. AL2023 supports TLS 1.3 and TLS 1.2 network protocols.

By default, AL2 comes with OpenSSL 1.0.2. You can build applications against OpenSSL 1.1.1.

For more information about OpenSSL, see the [OpenSSL migration guide](#).

For more information about security, see [Security updates and features](#).

## IMDSv2

By default, any instances launched with the AL2023 AMI require IMDSv2-only and your default hop limit will be set to 2 to allow for containerized workload support. This is done by setting the `imds-support` parameter to `v2.0`. For more information, see [Configure the AMI](#) in the *Amazon EC2 User Guide*.

 **Note**

The session token's time of validity can be anywhere between 1 second and 6 hours. The addresses to direct the API requests for IMDSv2 queries are the following:

- IPv4: 169.254.169.254
- IPv6: fd00:ec2::254

You can manually override these settings and enable IMDSv1 using Instance Metadata option launch properties. You can also use IAM controls to enforce different IMDS settings. For more information about setting up and using the Instance Metadata Service, see [Use IMDSv2](#), [Configure instance metadata options for new instances](#), and [Modify instance metadata options for existing instances](#), in the *Amazon EC2 User Guide*.

## Removal of log4j hotpatch (log4j-cve-2021-44228-hotpatch)

 **Note**

AL2023 doesn't ship with the `log4j-cve-2021-44228-hotpatch` package.

In response to [CVE-2021-44228](#), Amazon Linux released an RPM packaged version of the [Hotpatch for Apache Log4j](#) for AL1 and AL2. In the [announcement of the addition of the hotpatch to Amazon Linux](#) we noted that "Installing the hotpatch is not a replacement for updating to a log4j version that mitigates CVE-2021-44228 or CVE-2021-45046.".

The hotpatch was a mitigation to allow time to patch log4j. The first General Availability (GA) release of AL2023 was 15 months after [CVE-2021-44228](#), thus AL2023 doesn't ship with the hotpatch (enabled or not).

Users running their own log4j versions on Amazon Linux should ensure that they have updated to versions not affected by [CVE-2021-44228](#) or [CVE-2021-45046](#).

AL2023 provides guidance on [Updating AL2023](#) so that you can keep up to date with security patches. Security advisories are published on the [Amazon Linux Security Center](#).

## Deterministic upgrades for stability

With the deterministic upgrades through versioned repositories feature, every AL2023 AMI by default is locked to a specific repository version. You can use deterministic upgrades to achieve greater consistency among package versions and updates. Each release, major or minor, includes a specific repository version.

New with AL2023, deterministic upgrading by default is enabled. This is an improvement over the manual, incremental method of locking that's used in AL2 and other earlier versions.

For more information, see [Using Deterministic upgrades through versioned repository on AL2023](#).

## gp3 as default Amazon EBS volume type

The AL2023 AMI and AL2 both use the XFS file system on the root file system. For AL2023, the mkfsoptions for the root device file system are further optimized for Amazon EC2. AL2023 also supports a number of other file systems that you can use on other volumes to meet your specific requirements.

AL2023 AMIs use Amazon EBS gp3 volumes by default, whereas AL2 AMIs use Amazon EBS gp2 volumes by default. You can change the volume type when you launch an instance.

For more information about Amazon EBS volume types, see [Amazon EBS General Purpose Volumes](#).

For more information about launching an Amazon EC2 instance, see [Launch an instance](#) in the [Amazon EC2 User Guide](#).

## Unified Control Group hierarchy (cgroup v2)

A Control Group (cgroup) is a Linux kernel feature to hierarchically organize processes and distribute system resources between them. Control Groups are used extensively to implement a container runtime, and by systemd.

AL2 supports cgroupv1, and AL2023 supports cgroupv2. This is notable if running containerized workloads, such as when [Using AL2023 based Amazon ECS AMIs to host containerized workloads](#).

Although AL2023 still includes code that can make the system run using cgroupv1, this is not a recommended or supported configuration, and will be completely removed in a future major release of Amazon Linux.

There is extensive documentation regarding the [low-level Linux Kernel interfaces](#), as well as [systemd cgroup delegation documentation](#).

A common use case outside of containers is for creating systemd units that have limits placed on the system resources they can use. For more information, see [systemd.resource-control](#).

## systemd timers replace cron

The `cronie` package was installed by default on the AL2 AMI, providing support for the traditional `crontab` way of scheduling periodic tasks. In AL2023, `cronie` is not included by default. Therefore, support for `crontab` is no longer provided by default.

You can optionally install the `cronie` package to use classic `cron` jobs. We recommend that you migrate to systemd timers due to the added functionality provided by systemd.

## Improved toolchain: gcc, binutils, and glibc

AL2023 includes many of the same core packages as AL2.

We updated the following three core toolchain packages for AL2023.

Package name	AL2	AL2023
glibc	2.26	2.34
gcc	7.3	11.3
binutils	2.29	2.39

For more information, see [Core toolchain packages glibc, gcc, binutils](#).

For more information about optimizations, see [Performance and operational optimizations](#).

## systemd journal replaces rsyslog

In AL2023 the logging system package has changed from AL2. AL2023 doesn't install `rsyslog` by default, so the text based log files such as `/var/log/messages` that were available in AL2 aren't available by default. The default configuration for AL2023 is `systemd-journal`, which can be examined using `journalctl`. Although `rsyslog` is an optional package in AL2023, we recommend the new `systemd` based `journalctl` interface and related packages. For more information, see the [journalctl](#) manual page.

## Minimized package dependencies

Amazon Linux 2023 minimizes the dependency graph of many packages to provide a smaller footprint for applications. Notable changes from AL2 include the `curl-minimal` and `gnupg-minimal` packages, which significantly reduce the number of required packages while retaining commonly used functionality.

### Topics

- [Package changes for curl and libcurl](#)
- [GNU Privacy Guard \(GNUPG\)](#)

## Package changes for curl and libcurl

AL2023 separates out the common protocols and functionality of the `curl` and `libcurl` packages into `curl-minimal` and `libcurl-minimal`. This reduces the disk, memory, and dependency footprint for most users, and is the default package for AL2023 AMIs and containers.

If the full functionality of `curl` is required, for example for `gopher://` support, run the following commands to install the `curl-full` and `libcurl-full` packages.

```
$ dnf swap libcurl-minimal libcurl-full
```

```
$ dnf swap curl-minimal curl-full
```

## GNU Privacy Guard (GNUPG)

AL2023 separates out minimal and complete functionality for the gnupg2 package into gnupg2-minimal and gnupg2-full packages. By default, only the gnupg2-minimal package is installed. This provides the minimal functionality required to verify the digital signatures on rpm packages.

For more functionality from gnupg2, such as the ability to download keys from a key server, ensure that the gnupg2-full package is installed. Run the following command to swap gnupg2-minimal for gnupg2-full.

```
$ dnf swap gnupg2-minimal gnupg2-full
```

## Amazon Corretto as the default JVM

AL2023 ships with [Amazon Corretto](#) as the default (and only) Java Development Kit (JDK). All Java based packages in AL2023 are all built with Amazon Corretto 17.

If you are migrating from AL2, you can smoothly transition from the equivalent OpenJDK version on AL2 to Amazon Corretto.

## AWS CLI v2

AL2023 ships with AWS CLI version 2, whereas AL2 ships with version 1 of the AWS CLI.

## UEFI Preferred and Secure Boot

By default, any instances launched with the AL2023 AMI on instance types that support UEFI firmware will launch in UEFI mode. This is done by setting the Boot Mode AMI parameter to uefi-preferred. For more information, see [Boot Modes](#) in the *Amazon EC2 User Guide*.

On Amazon EC2 instance types that support UEFI Secure Boot, it is possible to enable Secure Boot in Amazon Linux 2023. For more information, see [UEFI Secure Boot on AL2023](#).

## SSH server default configuration changes

For the AL2023 AMI, we changed the types of sshd host keys that we generate with the release. We also dropped some legacy key types to avoid generating them at launch time. Clients must

support the `rsa-sha2-256` and `rsa-sha2-512` protocols or `ssh-ed25519` with use of an `ed25519` key. By default, `ssh-rsa` signatures are disabled.

Additionally, AL2023 configuration settings in the default `sshd_config` file contain `UseDNS=no`. This new setting means that DNS impairments are less likely to block your ability to establish ssh sessions with your instances. The tradeoff is that the `from=hostname.domain,hostname.domain` line entries in your `authorized_keys` files won't be resolved. Because `sshd` no longer attempts to resolve the DNS names, each comma separated `hostname.domain` value must be translated to a corresponding IP address.

For more information, see [Default SSH server configuration](#).

## AL2023 kernel changes from AL2

AL2023 brings the 6.1 kernel, as well as many configuration changes to further optimize Amazon Linux for the cloud. For most users, these changes should be completely transparent.

### IPv4 TTL

The TTL for IPv4 is configured via `sysctl`, with the default values being present in `/etc/sysctl.d/00-defaults.conf`. This value can be customized through the usual `sysctl` methods. For more information, see the `sysctl` man page.

AL2 set the `net.ipv4.ip_default_ttl` value to 255, while AL2023 sets it to 127. This brings Amazon Linux defaults in line with other major Linux distributions. It is not recommended to change this default without a demonstrated need to.

### Security focused kernel config changes

CONFIG option	AL2/4.14/aarch64	AL2/4.14/x86_64	AL2/5.10/aarch64	AL2/5.10/x86_64	AL2023/6.1/aarch64	AL2023/6.1/x86_64
<u><a href="#">CONFIG_BU</a></u> <u><a href="#">G_ON_DATA</a></u> <u><a href="#">_CORRUPTI</a></u> <u><a href="#">ON</a></u>	n	y	n	y	y	y
<u><a href="#">CONFIG_DE</a></u> <u><a href="#">FAULT_MMA</a></u>	4096	4096	4096	4096	65536	65536

<b>CONFIG option</b>	<b>AL2/4.14/aarch64</b>	<b>AL2/4.14/x86_64</b>	<b>AL2/5.10/aarch64</b>	<b>AL2/5.10/x86_64</b>	<b>AL2023/6.1/aarch64</b>	<b>AL2023/6.1/x86_64</b>
<u>P_MIN_ADD_R</u>						
<u>CONFIG_DEVMEM</u>	n	y	n	y	n	n
<u>CONFIG_DEVPORT</u>	n	y	n	y	n	n
<u>CONFIG_FORIFY_SOURCE</u>	n	y	n	y	y	y
<u>CONFIG_HARDENED_USERCOPY</u>	N/A	N/A	y	y	N/A	N/A
<u>CONFIG_INIT_ON_ALL_OCP_DEFAULT</u>	N/A	N/A	n	n	n	n
<u>CONFIG_INIT_ON_FREED_DEFAULT</u>	N/A	N/A	n	n	n	n
<u>CONFIG_IOMMU_DEFAULTRICT</u>	N/A	N/A	N/A	N/A	n	n
<u>CONFIG_LOAD_ISC_AUTOLOAD</u>	y	y	y	y	n	n

CONFIG option	AL2/4.14/aarch64	AL2/4.14/x86_64	AL2/5.10/aarch64	AL2/5.10/x86_64	AL2023/6.1/aarch64	AL2023/6.1/x86_64
<u><a href="#">CONFIG_SC_HED_CORE</a></u>	N/A	N/A	N/A	N/A	N/A	y
<u><a href="#">CONFIG_SC_HED_STACK_END_CHECK</a></u>	n	y	n	y	y	y
<u><a href="#">CONFIG_SE_CURITY_DM_ESG_RESTRICTIVE</a></u>	n	n	n	n	y	y
<u><a href="#">CONFIG_SE_SECURITY_LINUX_DISABLER</a></u>	y	y	y	y	n	n
<u><a href="#">CONFIG_SHUFFLE_PAGE_ALLOCATOR</a></u>	N/A	N/A	y	y	y	y
<u><a href="#">CONFIG_STAB_FREELIST_HARDENED</a></u>	n	y	y	y	y	y
<u><a href="#">CONFIG_STAB_FREELIST_RANDOM</a></u>	n	n	y	y	y	y

## x86-64 Specific Security focused kernel config changes

CONFIG option	AL2/4.14/x86_64	AL2/5.10/x86_64	AL2023/6.1/x86_64
<u><a href="#">CONFIG_AMD_IOMMU</a></u>	y	y	y
<u><a href="#">CONFIG_AMD_IOMMU_V2</a></u>	m	m	y
<u><a href="#">CONFIG_RANDOMIZE_MEMORY</a></u>	N/A	y	y

## aarch64 (ARM/Graviton) Specific Security focused kernel config changes

CONFIG option	AL2/4.14/aarch64	AL2/5.10/aarch64	AL2023/6.1/aarch64
<u><a href="#">CONFIG_AR_M64_PTR_AUTH</a></u>	N/A	y	y
<u><a href="#">CONFIG_AR_M64_PTR_A_UHT_KERNEL</a></u>	N/A	N/A	y
<u><a href="#">CONFIG_AR_M64_SW_TT_BR0_PAN</a></u>	y	y	y

## /dev/mem, /dev/kmem and /dev/port

Amazon Linux 2023 disables /dev/mem, and /dev/port (CONFIG\_DEVMEM and CONFIG\_DEVPORT) completely, building on the restrictions already in place in AL2.

The /dev/kmem code was completely removed from Linux in the 5.13 kernel, and while it was disabled in AL2, it is now not applicable to AL2023.

This option is one of the [Kernel Self Protection Project Recommended Settings](#).

## FORTIFY\_SOURCE

AL2023 enables CONFIG\_FORTIFY\_SOURCE on all supported architectures. This feature is a security hardening feature. Where the compiler can determine and validate the buffer sizes, this feature can detect buffer overflows in common string and memory functions.

This option is one of the [Kernel Self Protection Project Recommended Settings](#).

## Line Discipline autoload (CONFIG\_LDISC\_AUTOLOAD)

The AL2023 kernel will not automatically load line disciplines, such as by software using the TI0CSETD ioctl, unless the request comes from a process with the CAP\_SYS\_MODULE permissions.

This option is one of the [Kernel Self Protection Project Recommended Settings](#).

## dmesg access for unprivileged users (CONFIG\_SECURITY\_DMESG\_RESTRICT)

By default, AL2023 does not allow unprivileged users access to dmesg.

This option is one of the [Kernel Self Protection Project Recommended Settings](#).

## SELinux selinuxfs disable

AL2023 disables the deprecated CONFIG\_SECURITY\_SELINUX\_DISABLE kernel option, which enabled a runtime method of disabling SELinux prior to policy being loaded.

This option is one of the [Kernel Self Protection Project Recommended Settings](#).

## Other kernel configuration changes

CONFIG option	AL2/4.14/aarch64	AL2/4.14/x86_64	AL2/5.10/aarch64	AL2/5.10/x86_64	AL2023/6.1/aarch64	AL2023/6.1/x86_64
<a href="#"><u>CONFIG_HZ</u></a>	100	250	100	250	100	100
<a href="#"><u>CONFIG_NR_CPUS</u></a>	4096	8192	4096	8192	512	512

CONFIG option	AL2/4.14/aarch64	AL2/4.14/x86_64	AL2/5.10/aarch64	AL2/5.10/x86_64	AL2023/6.1/aarch64	AL2023/6.1/x86_64
<a href="#"><u>CONFIG_PA_NIC_ON_00_PS</u></a>	y	n	y	n	y	y
<a href="#"><u>CONFIG_PA_NIC_ON_00_PS_VALUE</u></a>	1	0	1	0	1	1
<a href="#"><u>CONFIG_PP_P</u></a>	m	m	m	m	n	n
<a href="#"><u>CONFIG_SLIP</u></a>	m	m	m	m	n	n
<a href="#"><u>CONFIG_XE_N_PV</u></a>	N/A	y	N/A	n	N/A	n

## CONFIG\_HZ

AL2023 sets CONFIG\_HZ to 100 on both x86-64 and aarch64 platforms.

## CONFIG\_NR\_CPUS

AL2023 sets CONFIG\_NR\_CPUS to a number closer to the maximum number of CPU cores found in Amazon EC2.

## Panic on OOPS

The AL2023 kernel will panic when it oopses. This feature is equivalent to booting with `oops=panic` on the kernel command line.

A kernel oops is where the kernel has detected an internal error which may affect the further reliability of the system.

## PPP and SLIP Support

AL2023 does not support the PPP or SLIP protocols.

## Xen PV Guest Support

AL2023 does not support running as a Xen PV guest.

## Kernel Filesystem support

There have been several changes in the file systems that the kernel in AL2 will support mounting, along with changes in the partitioning schemes that the kernel will parse.

CONFIG option	AL2/4.14/aarch64	AL2/4.14/x86_64	AL2/5.10/aarch64	AL2/5.10/x86_64	AL2023/6.1/aarch64	AL2023/6.1/x86_64
<u>CONFIG_AF_S_FS</u>	n	m	n	m	n	n
<u>CONFIG_AF_RXRPC</u>	n	m	n	m	n	n
<u>CONFIG_BS_D_DISKLAB_EL</u>	y	y	y	y	n	n
<u>CONFIG_CRAMFS</u>	m	m	m	m	n	n
<u>CONFIG_CRAMFS_BLOC_KDEV</u>	N/A	N/A	y	n	N/A	N/A
<u>CONFIG_DM_CLONE</u>	N/A	N/A	n	n	n	n
<u>CONFIG_DM_ERA</u>	m	n	m	n	n	n
<u>CONFIG_DM_INTEGRITY</u>	n	m	n	m	m	m

<b>CONFIG option</b>	<b>AL2/4.14/aarch64</b>	<b>AL2/4.14/x86_64</b>	<b>AL2/5.10/aarch64</b>	<b>AL2/5.10/x86_64</b>	<b>AL2023/6.1/aarch64</b>	<b>AL2023/6.1/x86_64</b>
<a href="#"><u>CONFIG_DM_LOG_WRITES</u></a>	n	n	m	m	m	m
<a href="#"><u>CONFIG_DM_SWITCH</u></a>	m	n	m	n	n	n
<a href="#"><u>CONFIG_DM_VERITY</u></a>	m	n	m	n	n	n
<a href="#"><u>CONFIG_ECRYPT_FS</u></a>	n	m	n	m	n	n
<a href="#"><u>CONFIG_EXFAT_FS</u></a>	N/A	N/A	m	m	m	m
<a href="#"><u>CONFIG_EXT2_FS</u></a>	n	m	n	m	n	n
<a href="#"><u>CONFIG_EXT3_FS</u></a>	n	m	n	m	n	n
<a href="#"><u>CONFIG_GFS2_FS</u></a>	m	m	m	m	n	n
<a href="#"><u>CONFIG_HFSPLUS_FS</u></a>	n	m	n	m	n	n
<a href="#"><u>CONFIG_HFS_S_FS</u></a>	n	m	n	m	n	n
<a href="#"><u>CONFIG_JFS_FS</u></a>	n	m	n	m	n	n

CONFIG option	AL2/4.14/aarch64	AL2/4.14/x86_64	AL2/5.10/aarch64	AL2/5.10/x86_64	AL2023/6.1/aarch64	AL2023/6.1/x86_64
<u><a href="#">CONFIG_LD_M_PARTITION</a></u>	n	y	n	y	n	n
<u><a href="#">CONFIG_MAC_PARTITION</a></u>	n	y	n	y	n	n
<u><a href="#">CONFIG_NFS_V2</a></u>	n	m	n	m	n	n
<u><a href="#">CONFIG_NTFS_FS</a></u>	n	m	n	n	n	n
<u><a href="#">CONFIG_ROMFS_FS</a></u>	n	m	n	m	n	n
<u><a href="#">CONFIG_SALARIS_X86_PARTITION</a></u>	n	y	n	y	n	n
<u><a href="#">CONFIG_SQUASHFS_ZSTD</a></u>	n	y	n	y	y	y
<u><a href="#">CONFIG_SUN_PARTITION</a></u>	n	y	n	y	n	n

## Andrew File System support (AFS)

The kernel is no longer built with support for the afs file system. AL2 did not ship with user-space support for afs.

## cramfs support

The kernel is no longer built with support for the `cramfs` file system. The successor in AL2023 is the `squashfs` file system.

## BSD disklabel support

The kernel is no longer built with support for BSD disk labels. If reading volumes with BSD disk labels is required, various BSDs can be launched.

## Device Mapper changes

There have been several changes to the Device Mapper targets configured in the AL2023 kernel.

## eCryptFs support

The `ecryptfs` file system has been deprecated in Amazon Linux. The user-space components of `ecryptfs` were present in AL1, removed in AL2, and AL2023 no longer builds the kernel with `ecryptfs` support.

## exFAT

Support for the exFAT file system was added in the 5.10 kernel in AL2. It was not present at AL2 launch with a 4.14 kernel. AL2023 continues to support the exFAT file system.

## The ext2, ext3, and ext4 file systems

AL2023 ships with the `CONFIG_EXT4_USE_FOR_EXT2` option, which means that the `ext4` file system code will be used to read legacy `ext2` file systems.

## `CONFIG_GFS2_FS`

The kernel is no longer built with `CONFIG_GFS2_FS`.

## Apple Extended HFS file system support (HFS+)

In AL2, only the x86-64 kernels were built with the `hfsplus` file system support. The AL2 5.15 kernel does not include `hfsplus` support on any architecture. In AL2023, we complete the deprecation of `hfsplus` support in Amazon Linux.

## HFS file system support

In AL2, only the x86-64 kernels were built with the hfs file system support. The AL2 5.15 kernel does not include hfs support on any architecture. In AL2023, we complete the deprecation of hfs support in Amazon Linux.

## JFS file system support

In AL2, only the x86-64 kernels were built with the jfs file system support. The AL2 5.15 kernel does not include jfs support on any architecture. Neither AL1 or AL2 shipped with JFS userspace. In AL2023, we complete the deprecation of jfs support in Amazon Linux.

The upstream Linux kernel is [considering the removal of JFS](#). Therefore, if you have data on a JFS file system, you should migrate it to another file system.

## Windows Logical Disk Manager (Dynamic Disk) support (CONFIG\_LDM\_PARTITION)

AL2023 no longer supports Windows 2000, Windows XP, or Windows Vista *dynamic disks* with MS-DOS style partitions. This code did not ever support the newer GPT based dynamic disks introduced with Windows Vista.

## Macintosh partition map support

AL2023 no longer supports the classic Macintosh partition map. Modern macOS versions will create modern GPT partition tables by default over this older type.

## NFSv2 support

AL2023 no longer supports NFSv2, but continues to support NFSv3, NFSv4, NFSv4.1, and NFSv4.2. We recommend that you migrate to NFSv3 or newer.

## NTFS (CONFIG\_NTFS\_FS)

The ntfs3 code replaced ntfs for accessing NTFS file systems on Amazon Linux as of the 5.10 kernel in AL2. AL2023 no longer includes the ntfs code, and relies exclusively on the ntfs3 code for accessing NTFS file systems.

## romfs file system

The squashfs file system is the successor of the romfs file system in Amazon Linux, and the AL2023 kernel is no longer built with support for romfs.

## Solaris x86 hard disk partition format

AL2023 no longer supports the Solaris x86 hard disk partition format.

## squashfszstd compression

AL2023 adds support for zstd compressed squashfs file systems on all supported architectures.

## Sun partition table support

AL2023 no longer includes support for the Sun partition table format (CONFIG\_SUN\_PARTITION).

## AMI and Container Image changes

There have been some changes to the packages included in AMIs and containers.

Amazon Linux 2023 introduces a [minimal container image](#), and support for building [bare-bones container images](#). For more information, see [Using AL2023 in containers](#).

## Comparing packages installed on Amazon Linux 2 and Amazon Linux 2023 AMIs

A comparison of the RPMs present on the Amazon Linux 2 and AL2023 standard AMIs.

Package	AL2 AMI	AL2023 AMI
acl	2.2.51	2.3.1
acpid	2.0.19	2.0.32
alternatives		1.15
amazon-chrony-config		4.3
<a href="#">amazon-ec2-net-utils</a>		2.4.1
amazon-linux-extras	2.0.3	
amazon-linux-extras-yum-plugin	2.0.3	

Package	AL2 AMI	AL2023 AMI
amazon-linux-repo-s3		2023.4.20240513
<a href="#"><u>amazon-linux-sb-keys</u></a>		2023.1
amazon-rpm-config		228
amazon-ssm-agent	3.3.131.0	3.3.380.0
at	3.1.13	3.1.23
attr	2.4.46	2.5.1
audit	2.8.1	3.0.6
audit-libs	2.8.1	3.0.6
authconfig	6.2.8	
aws-cfn-bootstrap	2.0	2.0
awscli	1.18.147	
awscli-2		2.15.30
basesystem	10.0	11
bash	4.2.46	5.2.15
bash-completion	2.1	2.11
bc	1.06.95	1.07.1
bind-export-libs	9.11.4	
bind-libs	9.11.4	9.16.48
bind-libs-lite	9.11.4	
bind-license	9.11.4	9.16.48

Package	AL2 AMI	AL2023 AMI
bind-utils	9.11.4	9.16.48
<a href="#"><u>binutils</u></a>	2.29.1	2.39
blktrace	1.0.5	
boost-date-time	1.53.0 (x86_64)	
boost-filesystem		1.75.0
boost-system	1.53.0 (x86_64)	1.75.0
boost-thread	1.53.0 (x86_64)	1.75.0
bridge-utils	1.5	
bzip2	1.0.6	1.0.8
bzip2-libs	1.0.6	1.0.8
ca-certificates	2023.2.64	2023.2.64
c-ares		1.19.0
checkpolicy		3.4
chkconfig	1.7.4	1.15
chrony	4.2	4.3
cloud-init	19.3	22.2.2
cloud-init-cfg-ec2		22.2.2
cloud-utils-growpart	0.31	0.31
coreutils	8.22	8.32
coreutils-common		8.32

Package	AL2 AMI	AL2023 AMI
cpio	2.12	2.13
cracklib	2.9.0	2.9.6
cracklib-dicts	2.9.0	2.9.6
<a href="#"><u>cronie</u></a>	1.4.11	
cronie-anacron	1.4.11	
crontabs	1.11	1.11
crypto-policies		20220428
crypto-policies-scripts		20220428
cryptsetup	1.7.4	2.6.1
cryptsetup-libs	1.7.4	2.6.1
<a href="#"><u>curl</u></a>	8.3.0	
<a href="#"><u>curl-minimal</u></a>		8.5.0
cyrus-sasl-lib	2.1.26	2.1.27
cyrus-sasl-plain	2.1.26	2.1.27
dbus	1.10.24	1.12.28
dbus-broker		32
dbus-common		1.12.28
dbus-libs	1.10.24	1.12.28
device-mapper	1.02.170	1.02.185
device-mapper-event	1.02.170	

Package	AL2 AMI	AL2023 AMI
device-mapper-event-libs	1.02.170	
device-mapper-libs	1.02.170	1.02.185
device-mapper-persistent-data	0.7.3	
dhclient	4.2.5	
dhcp-common	4.2.5	
dhcp-libs	4.2.5	
diffutils	3.3	3.8
dmidecode	3.2	
dmraid	1.0.0.rc16	
dmraid-events	1.0.0.rc16	
dnf		4.14.0
dnf-data		4.14.0
dnf-plugin-release-notification		1.2
dnf-plugins-core		4.3.0
dnf-plugin-support-info		1.2
dnf-utils		4.3.0
dosfstools	3.0.20	4.2
dracut	033	055

<b>Package</b>	<b>AL2 AMI</b>	<b>AL2023 AMI</b>
dracut-config-ec2	2.0	3.0
dracut-config-generic	033	055
dwz		0.14
dyninst	9.3.1 (x86_64)	10.2.1
e2fsprogs	1.42.9	1.46.5
e2fsprogs-libs	1.42.9	1.46.5
ec2-hibernate-agent	1.0.8	1.0.8
ec2-instance-connect	1.1	1.1
ec2-instance-connect-selinux	1.1	1.1
ec2-net-utils	1.7.3	
ec2-utils	1.2	2.2.0
ed	1.9	1.14.2
efibootmgr	15 (aarch64)	
efi-filesystem		5
efi-srpm-macros		5
efivar		38
efivar-libs	31 (aarch64)	38
elfutils-debuginfod-client		0.188

<b>Package</b>	<b>AL2 AMI</b>	<b>AL2023 AMI</b>
elfutils-default- ama-scope	0.176	0.188
elfutils-libelf	0.176	0.188
elfutils-libs	0.176	0.188
ethtool	4.8	5.15
expat	2.1.0	2.5.0
file	5.11	5.39
file-libs	5.11	5.39
filesystem	3.2	3.14
findutils	4.5.11	4.8.0
fipscheck	1.4.1	
fipscheck-lib	1.4.1	
fonts-srpm-macros		2.0.5
freetype	2.8	
fstirm		0.6.1
fuse-libs	2.9.2	2.9.9
gawk	4.0.2	5.1.0
gdbm	1.13	
gdbm-libs		1.19
gdisk	0.8.10	1.0.8
generic-logos	18.0.0	

Package	AL2 AMI	AL2023 AMI
GeoIP	1.5.0	
gettext	0.19.8.1	0.21
gettext-libs	0.19.8.1	0.21
ghc-srpm-macros		1.5.0
glib2	2.56.1	2.74.7
glibc	2.26	2.34
glibc-all-langpacks	2.26	2.34
glibc-common	2.26	2.34
glibc-gconv-extra		2.34
glibc-locale-source	2.26	2.34
glibc-minimal-langpack	2.26	
gmp	6.0.0	6.2.1
<a href="#"><u>gnupg2</u></a>	2.0.22	
<a href="#"><u>gnupg2-minimal</u></a>		2.3.7
gnutls		3.8.0
go-srpm-macros		3.2.0
gpgme	1.3.2	1.15.1
gpm-libs	1.20.7	1.20.7
grep	2.20	3.8
groff-base	1.22.2	1.22.4

<b>Package</b>	<b>AL2 AMI</b>	<b>AL2023 AMI</b>
grub2	2.06	
grub2-common	2.06	2.06
grub2-efi-aa64	2.06 (aarch64)	
grub2-efi-aa64-ec2	2.06 (aarch64)	2.06 (aarch64)
grub2-efi-aa64-modules	2.06 (noarch)	
grub2-efi-x64-ec2	2.06 (x86_64)	2.06 (x86_64)
grub2-pc	2.06 (x86_64)	
grub2-pc-modules	2.06 (noarch)	2.06
grub2-tools	2.06	2.06
grub2-tools-minimal	2.06	2.06
grubby	8.28	8.40
gssproxy	0.7.0	0.8.4
gzip	1.5	1.12
hardlink	1.3	
hibagent	1.1.0	
hostname	3.13	3.23
hunspell	1.3.2	1.7.0
hunspell-en	0.20121024	0.20140811.1
hunspell-en-GB	0.20121024	0.20140811.1
hunspell-en-US	0.20121024	0.20140811.1

Package	AL2 AMI	AL2023 AMI
hunspell-filesystem		1.7.0
hwdata	0.252	0.353
info	5.1	6.7
inih		49
initscripts	9.49.47	10.09
iproute	5.10.0	5.10.0
iptables	1.8.4	
iptables-libs	1.8.4	
iputils	20180629	20210202
irqbalance	1.7.0	1.9.0
jansson	2.10	2.14
jbigkit-libs	2.0	
jitterentropy		3.4.1
jq		1.7.1
json-c	0.11	0.14
kbd	1.15.5	2.4.0
kbd-legacy	1.15.5	
kbd-misc	1.15.5	2.4.0
kernel	5.10.215	6.1.90
kernel-livepatch-r epo-s3		2023.4.20240513

Package	AL2 AMI	AL2023 AMI
kernel-srpm-macros		1.0
kernel-tools	5.10.215	6.1.90
keyutils	1.5.8	1.6.3
keyutils-libs	1.5.8	1.6.3
kmod	25	29
kmod-libs	25	29
kpartx	0.4.9	
kpatch-runtime	0.9.4	0.9.7
krb5-libs	1.15.1	1.21
langtable	0.0.31	
langtable-data	0.0.31	
langtable-python	0.0.31	
less	458	608
libacl	2.2.51	2.3.1
libaio	0.3.109	0.3.111
libarchive		3.5.3
libargon2		20171227
libassuan	2.1.0	2.5.5
libattr	2.4.46	2.5.1
libbasicobjects	0.1.1	0.1.1

Package	AL2 AMI	AL2023 AMI
libblkid	2.30.2	2.37.4
libcap	2.54	2.48
libcap-ng	0.7.5	0.8.2
libcbor		0.7.0
libcollection	0.7.0	0.7.0
libcom_err	1.42.9	1.46.5
libcomps		0.1.20
libconfig	1.4.9	1.7.2
libcroco	0.6.12	
libcrypt	2.26	
<a href="#"><u>curl</u></a>	8.3.0	
<a href="#"><u>curl-minimal</u></a>		8.5.0
libdaemon	0.14	
<a href="#"><u>ldb</u></a>	5.3.21	5.3.28
libldb-utils	5.3.21	
libdhash		0.5.0
libdnf		0.69.0
libdrm	2.4.97	
libdwf	20130207 (x86_64)	
libeconf		0.4.0

Package	AL2 AMI	AL2023 AMI
libedit	3.0	3.1
libestr	0.1.9	
libev		4.33
libevent	2.0.21	2.1.12
libfastjson	0.99.4	
libfdisk	2.30.2	2.37.4
libffi	3.0.13	3.4.4
libfido2		1.10.0
libgcc	7.3.1	11.4.1
libgcrypt	1.5.3	1.10.2
libgomp	7.3.1	11.4.1
libgpg-error	1.12	1.42
libibverbs		48.0
libicu	50.2	
libidn	1.28	
libidn2	2.3.0	2.3.2
libini_config	1.3.1	1.3.1
libjpeg-turbo	2.0.90	
libkapi		1.4.0
libkapi-hmaccalc		1.4.0

<b>Package</b>	<b>AL2 AMI</b>	<b>AL2023 AMI</b>
liblldb		2.6.2
libmaxminddb		1.5.2
libmetalink	0.1.3	0.1.3
libmnl	1.0.3	1.0.4
libmodulemd		2.13.0
libmount	2.30.2	2.37.4
libnetfilter_conntrack	1.0.6	
libnfnetwork	1.0.1	
libnfsidmap	0.25	2.5.4
libnghttp2	1.41.0	1.59.0
libnl3	3.2.28	3.5.0
libnl3-cli	3.2.28	
libpath_utils	0.2.1	0.2.1
libpcap	1.5.3	1.10.1
libpciaccess	0.14 (x86_64)	
libpipeline	1.2.3	1.5.3
libpkgconf		1.8.0
libpng	1.5.13	
libpsl	0.21.5	0.21.1
libpwquality	1.2.3	1.4.4

<b>Package</b>	<b>AL2 AMI</b>	<b>AL2023 AMI</b>
libref_array	0.1.5	0.1.5
librepo		1.14.5
libreport-filesystem		2.15.2
libseccomp	2.5.2	2.5.3
libselinux	2.5	3.4
libselinux-utils	2.5	3.4
libsemanage	2.5	3.4
libsepolicy	2.5	3.4
libsigsegv		2.13
libsmartcols	2.30.2	2.37.4
libsolv		0.7.22
libss	1.42.9	1.46.5
libssh2	1.4.3	
libsss_certmap		2.9.4
libsss_idmap	1.16.5	2.9.4
libsss_nss_idmap	1.16.5	2.9.4
libsss_sudo		2.9.4
libstdc++	7.3.1	11.4.1
libstoragemgmt	1.6.1	1.9.4
libstoragemgmt-pyth hon	1.6.1	

<b>Package</b>	<b>AL2 AMI</b>	<b>AL2023 AMI</b>
libstoragegmt-python-clibs	1.6.1	
libsysfs	2.1.0	
libtalloc		2.3.4
libtasn1	4.10	4.19.0
libtdb		1.4.7
libteam	1.27	
libevent		0.13.0
libtextstyle		0.21
libtiff	4.0.3	
libtirpc	0.2.4	1.3.3
libunistring	0.9.3	0.9.10
libuser	0.60	0.63
libutempter	1.1.6	1.2.1
libuuid	2.30.2	2.37.4
libuv		1.47.0
libverto	0.2.5	0.3.2
libverto-libev		0.3.2
libverto-libevent	0.2.5	
libwebp	0.3.0	
libxcrypt		4.4.33

<b>Package</b>	<b>AL2 AMI</b>	<b>AL2023 AMI</b>
libxml2	2.9.1	2.10.4
libxml2-python	2.9.1	
libyaml	0.1.4	0.2.5
libzstd		1.5.5
lm_sensors-libs	3.4.0	3.6.0
lmdb-libs		0.9.29
logrotate	3.8.6	3.20.1
lsof	4.87	4.94.0
lua	5.1.4	
lua-libs		5.4.4
lua-srpm-macros		1
lvm2	2.02.187	
lvm2-libs	2.02.187	
lz4	1.7.5	
lz4-libs		1.9.4
make	3.82	
man-db	2.6.3	2.9.3
man-pages	3.53	5.10
man-pages-overrides	7.5.2	
mariadb-libs	5.5.68	

Package	AL2 AMI	AL2023 AMI
mdadm	4.0	
microcode_ctl	2.1 (x86_64)	2.1 (x86_64)
mlocate	0.26	
mpfr		4.1.0
mtr	0.92	
nano	2.9.8	5.8
ncurses	6.0	6.2
ncurses-base	6.0	6.2
ncurses-libs	6.0	6.2
nettle	2.7.1	3.8
net-tools	2.0	2.0
newt	0.52.15	0.52.21
newt-python	0.52.15	
nfs-utils	1.3.0	2.5.4
npth		1.6
nspr	4.35.0	4.35.0
nss	3.90.0	3.90.0
nss-pem	1.0.3	
nss-softokn	3.90.0	3.90.0
nss-softokn-freebl	3.90.0	3.90.0

<b>Package</b>	<b>AL2 AMI</b>	<b>AL2023 AMI</b>
nss-sysinit	3.90.0	3.90.0
nss-tools	3.90.0	
nss-util	3.90.0	3.90.0
ntsysv	1.7.4	1.15
numactl-libs	2.0.9	2.0.14
ocaml-srpm-macros		6
oniguruma		6.9.7.1
openblas-srpm-macros		2
openldap	2.4.44	2.4.57
openssh	7.4p1	8.7p1
openssh-clients	7.4p1	8.7p1
openssh-server	7.4p1	8.7p1
openssl	1.0.2k	3.0.8
openssl-libs	1.0.2k	3.0.8
openssl-pkcs11		0.4.12
os-prober	1.58	1.77
p11-kit	0.23.22	0.24.1
p11-kit-trust	0.23.22	0.24.1
package-notes-srpm-macros		0.4
pam	1.1.8	1.5.1

Package	AL2 AMI	AL2023 AMI
parted	3.1	3.4
passwd	0.79	0.80
pciutils	3.5.1	3.7.0
pciutils-libs	3.5.1	3.7.0
<a href="#"><u>pcre</u></a>	8.32	
pcre2	10.23	10.40
pcre2-syntax		10.40
<a href="#"><u>perl</u></a>	5.16.3	
perl-Carp	1.26	1.50
perl-Class-Struct		0.66
perl-constant	1.27	1.33
perl-DynaLoader		1.47
perl-Encode	2.51	3.15
perl-Errno		1.30
perl-Exporter	5.68	5.74
perl-Fcntl		1.13
perl-File-Basename		2.85
perl-File-Path	2.09	2.18
perl-File-stat		1.09
perl-File-Temp	0.23.01	0.231.100

<b>Package</b>	<b>AL2 AMI</b>	<b>AL2023 AMI</b>
perl-Filter	1.49	
perl-Getopt-Long	2.40	2.52
perl-Getopt-Std		1.12
perl-HTTP-Tiny	0.033	0.078
perl-if		0.60.800
perl-interpreter		5.32.1
perl-Io		1.43
perl-IPC-Open3		1.21
perl-libs	5.16.3	5.32.1
perl-macros	5.16.3	
perl-MIME-Base64		3.16
perl-mro		1.23
perl-overload		1.31
perl-overloading		0.02
perl-parent	0.225	0.238
perl-PathTools	3.40	3.78
perl-Pod-Escapes	1.04	1.07
perl-podlators	2.5.1	4.14
perl-Pod-Perldoc	3.20	3.28.01
perl-Pod-Simple	3.28	3.42

<b>Package</b>	<b>AL2 AMI</b>	<b>AL2023 AMI</b>
perl-Pod-Usage	1.63	2.01
perl-POSIX		1.94
perl-Scalar-List-Utilities	1.27	1.56
perl-SelectSaver		1.02
perl-Socket	2.010	2.032
perl-srpm-macros		1
perl-Storable	2.45	3.21
perl-subs		1.03
perl-Symbol		1.08
perl-Term-ANSIColor		5.01
perl-Term-Cap		1.17
perl-Text-ParseWords	3.29	3.30
perl-Text-Tabs+Wrap		2021.0726
perl-threads	1.87	
perl-threads-shared	1.43	
perl-Time-HiRes	1.9725	
perl-Time-Local	1.2300	1.300
perl-vars		1.05
pinentry	0.8.1	
pkgconf		1.8.0

Package	AL2 AMI	AL2023 AMI
pkgconfig	0.27.1	
pkgconf-m4		1.8.0
pkgconf-pkg-config		1.8.0
plymouth	0.8.9	
plymouth-core-libs	0.8.9	
plymouth-scripts	0.8.9	
pm-utils	1.4.1	
policycoreutils	2.5	3.4
policycoreutils-python-utils		3.4
popt	1.13	1.18
postfix	2.10.1	
procps-ng	3.3.10	3.3.17
protobuf-c		1.4.1
psacct	6.6.1	6.6.4
psmisc	22.20	23.4
pth	2.0.7	
publicsuffix-list-dafsa	20240208	20240212
pygpgme	0.3	
pyliblzma	0.5.3	

Package	AL2 AMI	AL2023 AMI
pystache	0.5.3	
<a href="#">python</a>	2.7.18	
python2-botocore	1.18.6	
python2-colorama	0.3.9	
python2-cryptography	1.7.2	
python2-dateutil	2.6.1	
python2-futures	3.0.5	
python2-jmespath	0.9.3	
python2-jsonschema	2.5.1	
python2-oauthlib	2.0.1	
python2-pyasn1	0.1.9	
python2-rpm	4.11.3	
python2-rsa	3.4.1	
python2-s3transfer	0.3.3	
python2-setuptools	41.2.0	
python2-six	1.11.0	
python3	3.7.16	3.9.16
python3-attrs		20.3.0
python3-audit		3.0.6
python3-awscrt		0.19.19

Package	AL2 AMI	AL2023 AMI
python3-babel		2.9.1
python3-cffi		1.14.5
python3-chardet		4.0.0
python3-colorama		0.4.4
python3-configobj		5.0.6
python3-cryptography		36.0.1
python3-daemon	2.2.3	2.3.0
python3-dateutil		2.8.1
python3-dbus		1.2.18
python3-distro		1.5.0
python3-dnf		4.14.0
python3-dnf-plugins-core		4.3.0
python3-docutils	0.14	0.16
python3-gpg		1.15.1
python3-hawkey		0.69.0
python3-idna		2.10
python3-jinja2		2.11.3
python3-jmespath		0.10.0
python3-jsonpatch		1.21
python3-jsonpointer		2.0

Package	AL2 AMI	AL2023 AMI
python3-jsonschema		3.2.0
python3-libcomps		0.1.20
python3-libdnf		0.69.0
python3-libs	3.7.16	3.9.16
python3-libselinux		3.4
python3-libsemanage		3.4
python3-libstorage mgmt		1.9.4
python3-lockfile	0.11.0	0.12.2
python3-markupsafe		1.1.1
python3-netifaces		0.10.6
python3-oauthlib		3.0.2
python3-pip	20.2.2	
python3-pip-wheel		21.3.1
python3-ply		3.11
python3-policycore utils		3.4
python3-prettytable		0.7.2
python3-prompt-too lkit		3.0.24
python3-pycparser		2.20

Package	AL2 AMI	AL2023 AMI
python3-persistent		0.17.3
python3-pyserial		3.4
python3-pysocks		1.7.1
python3-pystache	0.5.4	
python3-pytz		2022.7.1
python3-pyyaml		5.4.1
python3-requests		2.25.1
python3-rpm		4.16.1.3
python3-ruamel-yaml		0.16.6
python3-ruamel-yaml- clib		0.1.2
python3-setools		4.4.1
python3-setuptools	49.1.3	59.6.0
python3-setuptools- wheel		59.6.0
python3-simplejson	3.2.0	
python3-six		1.15.0
python3-systemd		235
python3-urllib3		1.25.10
python3-wcwidth		0.2.5
python-babel	0.9.6	

<b>Package</b>	<b>AL2 AMI</b>	<b>AL2023 AMI</b>
python-backports	1.0	
python-backports-s sl_match_hostname	3.5.0.1	
python-cffi	1.6.0	
python-chardet	2.2.1	
python-chevron		0.13.1
python-configobj	4.7.2	
python-daemon	1.6	
python-devel	2.7.18	
python-docutils	0.12	
python-enum34	1.0.4	
python-idna	2.4	
python-iniparse	0.4	
python-ipaddress	1.0.16	
python-jinja2	2.7.2	
python-jsonpatch	1.2	
python-jsonpointer	1.9	
python-jwcrypto	0.4.2	
python-kitchen	1.1.1	
python-libs	2.7.18	
python-lockfile	0.9.1	

<b>Package</b>	<b>AL2 AMI</b>	<b>AL2023 AMI</b>
python-markupsafe	0.11	
python-pillow	2.0.0	
python-ply	3.4	
python-pycparser	2.14	
python-pycurl	7.19.0	
python-repoze-lru	0.4	
python-requests	2.6.0	
python-simplejson	3.2.0	
python-srpm-macros		3.9
python-urlgrabber	3.10	
python-urllib3	1.25.9	
pyxattr	0.5.1	
PyYAML	3.10	
qrencode-libs	3.4.1	
quota	4.01	4.06
quota-nls	4.01	4.06
rdate	1.4	
readline	6.2	8.1
rng-tools	6.8	6.14
rootfiles	8.1	8.1

Package	AL2 AMI	AL2023 AMI
rpcbind	0.2.0	1.2.6
rpm	4.11.3	4.16.1.3
rpm-build-libs	4.11.3	4.16.1.3
rpm-libs	4.11.3	4.16.1.3
rpm-plugin-selinux		4.16.1.3
rpm-plugin-systemd-inhibit	4.11.3	4.16.1.3
rpm-sign-libs		4.16.1.3
rsync	3.1.2	3.2.6
rsyslog	8.24.0	
rust-srpm-macros		21
sbsigntools		0.9.4
scl-utils	20130529	
screen	4.1.0	4.8.0
sed	4.2.2	4.8
selinux-policy	3.13.1	37.22
selinux-policy-targeted	3.13.1	37.22
setserial	2.17	
setup	2.8.71	2.13.7
setup tool	1.19.11	

<b>Package</b>	<b>AL2 AMI</b>	<b>AL2023 AMI</b>
sgpio	1.2.0.10	
shadow-utils	4.1.5.1	4.9
shared-mime-info	1.8	
slang	2.2.4	2.3.2
sqlite	3.7.17	
sqlite-libs		3.40.0
sssd-client	1.16.5	2.9.4
sssd-common		2.9.4
sssd-kcm		2.9.4
sssd-nfs-idmap		2.9.4
strace	4.26	6.8
sudo	1.8.23	1.9.15
sysctl-defaults	1.0	1.0
sysstat	10.1.5	12.5.6
systemd	219	252.16
systemd-libs	219	252.16
systemd-networkd		252.16
systemd-pam		252.16
systemd-resolved		252.16
systemd-sysv	219	

Package	AL2 AMI	AL2023 AMI
systemd-udev		252.16
system-release	2	2023.4.20240513
systemtap-runtime	4.5	4.8
sysvinit-tools	2.88	
tar	1.26	1.34
tbb		2020.3
tcp_wrappers	7.6	
tcp_wrappers-libs	7.6	
tcpdump	4.9.2	4.99.1
tcsh	6.18.01	6.24.07
teamd	1.27	
time	1.7	1.9
traceroute	2.0.22	2.1.3
tzdata	2024a	2024a
unzip	6.0	6.0
update-motd	1.1.2	2.2
usermode	1.111	
userspace-rcu		0.12.1
ustr	1.0.4	
util-linux	2.30.2	2.37.4

Package	AL2 AMI	AL2023 AMI
util-linux-core		2.37.4
vim-common	9.0.2153	9.0.2153
vim-data	9.0.2153	9.0.2153
vim-enhanced	9.0.2153	9.0.2153
vim-filesystem	9.0.2153	9.0.2153
vim-minimal	9.0.2153	9.0.2153
virt-what	1.18	
wget	1.14	1.21.3
which	2.20	2.21
words	3.0	3.0
xfsdump	3.1.8	3.1.11
xfsprogs	5.0.0	5.18.0
xxd	9.0.2153	9.0.2153
xxhash-libs		0.8.0
xz	5.2.2	5.2.5
xz-libs	5.2.2	5.2.5
yajl	2.0.4	
yum	3.4.3	4.14.0
yum-langpacks	0.4.2	
yum-metadata-parser	1.1.4	

Package	AL2 AMI	AL2023 AMI
yum-plugin-priorities	1.1.31	
yum-utils	1.1.31	
zip	3.0	3.0
zlib	1.2.7	1.2.11
zram-generator		1.1.2
zram-generator-defaults		1.1.2
zstd		1.5.5

## Comparing packages installed on Amazon Linux 2 and Amazon Linux 2023 Minimal AMIs

A comparison of the RPMs present on the Amazon Linux 2 and AL2023 Minimal AMIs.

Package	AL2 Minimal	AL2023 Minimal
acl	2.2.51	
alternatives		1.15
amazon-chrony-config		4.3
<a href="#"><u>amazon-ec2-net-utils</u></a>		2.4.1
amazon-linux-extras	2.0.3	
amazon-linux-repo-s3		2023.4.20240513
<a href="#"><u>amazon-linux-sb-keys</u></a>		2023.1

<b>Package</b>	<b>AL2 Minimal</b>	<b>AL2023 Minimal</b>
audit	2.8.1	3.0.6
audit-libs	2.8.1	3.0.6
authconfig	6.2.8	
awscli-2		2.15.30
basesystem	10.0	11
bash	4.2.46	5.2.15
bind-export-libs	9.11.4	
bzip2-libs	1.0.6	1.0.8
ca-certificates	2023.2.64	2023.2.64
checkpolicy		3.4
chkconfig	1.7.4	
chrony	4.2	4.3
cloud-init	19.3	22.2.2
cloud-init-cfg-ec2		22.2.2
cloud-utils-growpart	0.31	0.31
coreutils	8.22	8.32
coreutils-common		8.32
cpio	2.12	2.13
cracklib	2.9.0	2.9.6
cracklib-dicts	2.9.0	2.9.6

<b>Package</b>	<b>AL2 Minimal</b>	<b>AL2023 Minimal</b>
<a href="#"><u>cronie</u></a>	1.4.11	
cronie-anacron	1.4.11	
crontabs	1.11	
crypto-policies		20220428
cryptsetup-libs	1.7.4	2.6.1
<a href="#"><u>curl</u></a>	8.3.0	
<a href="#"><u>curl-minimal</u></a>		8.5.0
cyrus-sasl-lib	2.1.26	2.1.27
dbus	1.10.24	1.12.28
dbus-broker		32
dbus-common		1.12.28
dbus-libs	1.10.24	1.12.28
device-mapper	1.02.170	1.02.185
device-mapper-libs	1.02.170	1.02.185
dhclient	4.2.5	
dhcp-common	4.2.5	
dhcp-libs	4.2.5	
diffutils	3.3	3.8
dnf		4.14.0
dnf-data		4.14.0

<b>Package</b>	<b>AL2 Minimal</b>	<b>AL2023 Minimal</b>
dnf-plugin-release-notification		1.2
dnf-plugins-core		4.3.0
dnf-plugin-support-info		1.2
dracut	033	055
dracut-config-ec2	2.0	3.0
dracut-config-generic	033	055
e2fsprogs	1.42.9	1.46.5
e2fsprogs-libs	1.42.9	1.46.5
ec2-utils	1.2	2.2.0
efibootmgr	15 (aarch64)	
efi-filesystem		5
efivar		38
efivar-libs	31 (aarch64)	38
elfutils-default-yma-scope	0.176	0.188
elfutils-libelf	0.176	0.188
elfutils-libs	0.176	0.188
expat	2.1.0	2.5.0
file	5.11	5.39

<b>Package</b>	<b>AL2 Minimal</b>	<b>AL2023 Minimal</b>
file-libs	5.11	5.39
filesystem	3.2	3.14
findutils	4.5.11	4.8.0
fipscheck	1.4.1	
fipscheck-lib	1.4.1	
freetype	2.8	
fuse-libs	2.9.2	2.9.9
gawk	4.0.2	5.1.0
gdbm	1.13	
gdbm-libs		1.19
gdisk	0.8.10	1.0.8
gettext	0.19.8.1	0.21
gettext-libs	0.19.8.1	0.21
glib2	2.56.1	2.74.7
glibc	2.26	2.34
glibc-all-langpacks	2.26	2.34
glibc-common	2.26	2.34
glibc-locale-source	2.26	2.34
glibc-minimal-langpack	2.26	
gmp	6.0.0	6.2.1

<b>Package</b>	<b>AL2 Minimal</b>	<b>AL2023 Minimal</b>
<a href="#"><u>gnupg2</u></a>	2.0.22	
<a href="#"><u>gnupg2-minimal</u></a>		2.3.7
gnutls		3.8.0
gpgme	1.3.2	1.15.1
grep	2.20	3.8
groff-base	1.22.2	1.22.4
grub2	2.06	
grub2-common	2.06	2.06
grub2-efi-aa64	2.06 (aarch64)	
grub2-efi-aa64-ec2	2.06 (aarch64)	2.06 (aarch64)
grub2-efi-aa64-modules	2.06 (noarch)	
grub2-efi-x64-ec2	2.06 (x86_64)	2.06 (x86_64)
grub2-pc	2.06 (x86_64)	
grub2-pc-modules	2.06 (noarch)	2.06
grub2-tools	2.06	2.06
grub2-tools-minimal	2.06	2.06
grubby	8.28	8.40
gzip	1.5	1.12
hardlink	1.3	
hostname	3.13	3.23

<b>Package</b>	<b>AL2 Minimal</b>	<b>AL2023 Minimal</b>
hwdata		0.353
info	5.1	
inih		49
initscripts	9.49.47	10.09
iproute	5.10.0	5.10.0
iptables	1.8.4	
iptables-libs	1.8.4	
iputils	20180629	20210202
irqbalance	1.7.0	1.9.0
jansson		2.14
jitterentropy		3.4.1
jq		1.7.1
json-c		0.14
kbd		2.4.0
kbd-misc		2.4.0
kernel	4.14.343	6.1.90
kernel-livepatch-repo-s3		2023.4.20240513
keyutils-libs	1.5.8	1.6.3
kmod	25	29
kmod-libs	25	29

Package	AL2 Minimal	AL2023 Minimal
kpartx	0.4.9	
krb5-libs	1.15.1	1.21
less	458	608
libacl	2.2.51	2.3.1
libarchive		3.5.3
libargon2		20171227
libassuan	2.1.0	2.5.5
libattr	2.4.46	2.5.1
libblkid	2.30.2	2.37.4
libcap	2.54	2.48
libcap-ng	0.7.5	0.8.2
libcbor		0.7.0
libcom_err	1.42.9	1.46.5
libcomps		0.1.20
libcroco	0.6.12	
libcrypt	2.26	
<a href="#"><u>libcurl</u></a>	8.3.0	
<a href="#"><u>libcurl-minimal</u></a>		8.5.0
<a href="#"><u>libdb</u></a>	5.3.21	5.3.28
libdb-utils	5.3.21	

<b>Package</b>	<b>AL2 Minimal</b>	<b>AL2023 Minimal</b>
libdnf		0.69.0
libeconf		0.4.0
libedit	3.0	3.1
libestr	0.1.9	
libfastjson	0.99.4	
libfdisk	2.30.2	2.37.4
libffi	3.0.13	3.4.4
libfido2		1.10.0
libgcc	7.3.1	11.4.1
libgcrypt	1.5.3	1.10.2
libgomp	7.3.1	11.4.1
libgpg-error	1.12	1.42
libicu	50.2	
libidn	1.28	
libidn2	2.3.0	2.3.2
libkapi		1.4.0
libkapi-hmaccalc		1.4.0
libmetalink	0.1.3	
libmn1	1.0.3	1.0.4
libmodulemd		2.13.0

<b>Package</b>	<b>AL2 Minimal</b>	<b>AL2023 Minimal</b>
libmount	2.30.2	2.37.4
libnetfilter_conntrack	1.0.6	
libnfnetlink	1.0.1	
libnnghttp2	1.41.0	1.59.0
libpcap	1.5.3	
libpipeline	1.2.3	1.5.3
libpng	1.5.13	
libpsl	0.21.5	0.21.1
libpwquality	1.2.3	1.4.4
librepo		1.14.5
libreport-fs		2.15.2
libseccomp	2.5.2	2.5.3
libselinux	2.5	3.4
libselinux-utils	2.5	3.4
libsemanage	2.5	3.4
libsepolicy	2.5	3.4
libsigsegv		2.13
libsmartcols	2.30.2	2.37.4
libsolv		0.7.22
libss	1.42.9	1.46.5

<b>Package</b>	<b>AL2 Minimal</b>	<b>AL2023 Minimal</b>
libssh2	1.4.3	
libstdc++	7.3.1	11.4.1
libsysfs	2.1.0	
libtasn1	4.10	4.19.0
libtextstyle		0.21
libunistring	0.9.3	0.9.10
libuser	0.60	0.63
libutempter	1.1.6	1.2.1
libuuid	2.30.2	2.37.4
libverto	0.2.5	0.3.2
libxcrypt		4.4.33
libxml2	2.9.1	2.10.4
libyaml	0.1.4	0.2.5
libzstd		1.5.5
logrotate	3.8.6	3.20.1
lua	5.1.4	
lua-libs		5.4.4
lz4	1.7.5	
lz4-libs		1.9.4
make	3.82	

<b>Package</b>	<b>AL2 Minimal</b>	<b>AL2023 Minimal</b>
man-db	2.6.3	2.9.3
mariadb-libs	5.5.68	
microcode_ctl	2.1 (x86_64)	2.1 (x86_64)
mpfr		4.1.0
ncurses	6.0	6.2
ncurses-base	6.0	6.2
ncurses-libs	6.0	6.2
nettle	2.7.1	3.8
net-tools	2.0	2.0
newt	0.52.15	
newt-python	0.52.15	
npth		1.6
nspr	4.35.0	
nss	3.90.0	
nss-pem	1.0.3	
nss-softokn	3.90.0	
nss-softokn-freebl	3.90.0	
nss-sysinit	3.90.0	
nss-tools	3.90.0	
nss-util	3.90.0	

Package	AL2 Minimal	AL2023 Minimal
numactl-libs	2.0.9	2.0.14
oniguruma		6.9.7.1
openldap	2.4.44	2.4.57
openssh	7.4p1	8.7p1
openssh-clients	7.4p1	8.7p1
openssh-server	7.4p1	8.7p1
openssl	1.0.2k	3.0.8
openssl-libs	1.0.2k	3.0.8
openssl-pkcs11		0.4.12
os-prober	1.58	1.77
p11-kit	0.23.22	0.24.1
p11-kit-trust	0.23.22	0.24.1
pam	1.1.8	1.5.1
passwd	0.79	0.80
pciutils		3.7.0
pciutils-libs		3.7.0
<u>pcre</u>	8.32	
pcre2	10.23	10.40
pcre2-syntax		10.40
pinentry	0.8.1	

<b>Package</b>	<b>AL2 Minimal</b>	<b>AL2023 Minimal</b>
pkgconfig	0.27.1	
policycoreutils	2.5	3.4
popt	1.13	1.18
postfix	2.10.1	
procps-ng	3.3.10	3.3.17
psmisc	22.20	23.4
pth	2.0.7	
publicsuffix-list-dafsa	20240208	20240212
pygpgme	0.3	
pyliblzma	0.5.3	
<a href="#"><u>python</u></a>	2.7.18	
python2-cryptography	1.7.2	
python2-jsonschema	2.5.1	
python2-oauthlib	2.0.1	
python2-pyasn1	0.1.9	
python2-rpm	4.11.3	
python2-setuptools	41.2.0	
python2-six	1.11.0	
python3		3.9.16
python3-attrs		20.3.0

<b>Package</b>	<b>AL2 Minimal</b>	<b>AL2023 Minimal</b>
python3-audit		3.0.6
python3-awscrt		0.19.19
python3-babel		2.9.1
python3-cffi		1.14.5
python3-chardet		4.0.0
python3-colorama		0.4.4
python3-configobj		5.0.6
python3-cryptography		36.0.1
python3-dateutil		2.8.1
python3-dbus		1.2.18
python3-distro		1.5.0
python3-dnf		4.14.0
python3-dnf-plugins-core		4.3.0
python3-docutils		0.16
python3-gpg		1.15.1
python3-hawkey		0.69.0
python3-idna		2.10
python3-jinja2		2.11.3
python3-jmespath		0.10.0
python3-jsonpatch		1.21

<b>Package</b>	<b>AL2 Minimal</b>	<b>AL2023 Minimal</b>
python3-jsonpointer		2.0
python3-jsonschema		3.2.0
python3-libcomps		0.1.20
python3-libdnf		0.69.0
python3-libs		3.9.16
python3-libselinux		3.4
python3-libsemanage		3.4
python3-markupsafe		1.1.1
python3-netifaces		0.10.6
python3-oauthlib		3.0.2
python3-pip-wheel		21.3.1
python3-ply		3.11
python3-policycoreutils		3.4
python3-prettytable		0.7.2
python3-prompt-toolkit		3.0.24
python3-pycparser		2.20
python3-pyrsistent		0.17.3
python3-pyserial		3.4
python3-pysocks		1.7.1

<b>Package</b>	<b>AL2 Minimal</b>	<b>AL2023 Minimal</b>
python3-pytz		2022.7.1
python3-pyyaml		5.4.1
python3-requests		2.25.1
python3-rpm		4.16.1.3
python3-ruamel-yaml		0.16.6
python3-ruamel-yaml- clib		0.1.2
python3-setools		4.4.1
python3-setuptools		59.6.0
python3-setuptools- wheel		59.6.0
python3-six		1.15.0
python3-systemd		235
python3-urllib3		1.25.10
python3-wcwidth		0.2.5
python-babel	0.9.6	
python-backports	1.0	
python-backports-s sl_match_hostname	3.5.0.1	
python-cffi	1.6.0	
python-chardet	2.2.1	

<b>Package</b>	<b>AL2 Minimal</b>	<b>AL2023 Minimal</b>
python-configobj	4.7.2	
python-devel	2.7.18	
python-enum34	1.0.4	
python-idna	2.4	
python-iniparse	0.4	
python-ipaddress	1.0.16	
python-jinja2	2.7.2	
python-jsonpatch	1.2	
python-jsonpointer	1.9	
python-jwcrypto	0.4.2	
python-libs	2.7.18	
python-markupsafe	0.11	
python-ply	3.4	
python-pycparser	2.14	
python-pycurl	7.19.0	
python-repoze-lru	0.4	
python-requests	2.6.0	
python-urlgrabber	3.10	
python-urllib3	1.25.9	
pyxattr	0.5.1	

<b>Package</b>	<b>AL2 Minimal</b>	<b>AL2023 Minimal</b>
PyYAML	3.10	
qrencode-libs	3.4.1	
readline	6.2	8.1
rng-tools	6.8	6.14
rootfiles	8.1	8.1
rpm	4.11.3	4.16.1.3
rpm-build-libs	4.11.3	4.16.1.3
rpm-libs	4.11.3	4.16.1.3
rpm-plugin-selinux		4.16.1.3
rpm-plugin-systemd-inhibit	4.11.3	4.16.1.3
rpm-sign-libs		4.16.1.3
rsyslog	8.24.0	
sbsigntools		0.9.4
sed	4.2.2	4.8
selinux-policy	3.13.1	37.22
selinux-policy-targeted	3.13.1	37.22
setup	2.8.71	2.13.7
shadow-utils	4.1.5.1	4.9
shared-mime-info	1.8	

<b>Package</b>	<b>AL2 Minimal</b>	<b>AL2023 Minimal</b>
slang	2.2.4	
sqlite	3.7.17	
sqlite-libs		3.40.0
sudo	1.8.23	1.9.15
sysctl-defaults	1.0	1.0
systemd	219	252.16
systemd-libs	219	252.16
systemd-networkd		252.16
systemd-pam		252.16
systemd-resolved		252.16
systemd-sysv	219	
systemd-udev		252.16
system-release	2	2023.4.20240513
sysvinit-tools	2.88	
tar	1.26	1.34
tcp_wrappers-libs	7.6	
tzdata	2024a	2024a
update-motd	1.1.2	2.2
userspace-rcu		0.12.1
ustr	1.0.4	

Package	AL2 Minimal	AL2023 Minimal
util-linux	2.30.2	2.37.4
util-linux-core		2.37.4
vim-data	9.0.2153	9.0.2153
vim-minimal	9.0.2153	9.0.2153
which	2.20	2.21
xfsprogs	5.0.0	5.18.0
xz	5.2.2	5.2.5
xz-libs	5.2.2	5.2.5
yum	3.4.3	4.14.0
yum-metadata-parser	1.1.4	
yum-plugin-priorities	1.1.31	
zlib	1.2.7	1.2.11
zram-generator		1.1.2
zram-generator-defaults		1.1.2
zstd		1.5.5

## Comparing packages installed on Amazon Linux 2 and Amazon Linux 2023 base container images

A comparison of the RPMs present on the Amazon Linux 2 and AL2023 base container images.

Package	AL2 Container	AL2023 Container
alternatives		1.15
amazon-linux-extras	2.0.3	
amazon-linux-repo-cdn		2023.4.20240513
audit-libs		3.0.6
basesystem	10.0	11
bash	4.2.46	5.2.15
bzip2-libs	1.0.6	1.0.8
ca-certificates	2023.2.64	2023.2.64
chkconfig	1.7.4	
coreutils	8.22	
coreutils-single		8.32
cpio	2.12	
crypto-policies		20220428
<a href="#"><u>curl</u></a>	8.3.0	
<a href="#"><u>curl-minimal</u></a>		8.5.0
cyrus-sasl-lib	2.1.26	
diffutils	3.3	
dnf		4.14.0
dnf-data		4.14.0

Package	AL2 Container	AL2023 Container
elfutils-default- ama-scope		0.188
elfutils-libelf	0.176	0.188
elfutils-libs		0.188
expat	2.1.0	2.5.0
file-libs	5.11	5.39
filesystem	3.2	3.14
findutils	4.5.11	
gawk	4.0.2	5.1.0
gdbm	1.13	
gdbm-libs		1.19
glib2	2.56.1	2.74.7
glibc	2.26	2.34
glibc-common	2.26	2.34
glibc-langpack-en	2.26	
glibc-minimal-lang pack	2.26	2.34
gmp	6.0.0	6.2.1
<a href="#">gnupg2</a>	2.0.22	
<a href="#"><u>gnupg2-minimal</u></a>		2.3.7
gpgme	1.3.2	1.15.1

Package	AL2 Container	AL2023 Container
grep	2.20	3.8
info	5.1	
json-c		0.14
keyutils-libs	1.5.8	1.6.3
krb5-libs	1.15.1	1.21
libacl	2.2.51	2.3.1
libarchive		3.5.3
libassuan	2.1.0	2.5.5
libattr	2.4.46	2.5.1
libblkid	2.30.2	2.37.4
libcap	2.54	2.48
libcap-ng		0.8.2
libcom_err	1.42.9	1.46.5
libcomps		0.1.20
libcrypt	2.26	
<u>curl</u>	8.3.0	
<u>curl-minimal</u>		8.5.0
<u>libdb</u>	5.3.21	
libdb-utils	5.3.21	
libdnf		0.69.0

<b>Package</b>	<b>AL2 Container</b>	<b>AL2023 Container</b>
libffi	3.0.13	3.4.4
libgcc	7.3.1	11.4.1
libgcrypt	1.5.3	1.10.2
libgomp		11.4.1
libgpg-error	1.12	1.42
libidn2	2.3.0	2.3.2
libmetalink	0.1.3	
libmodulemd		2.13.0
libmount	2.30.2	2.37.4
libnghttp2	1.41.0	1.59.0
libpsl	0.21.5	0.21.1
librepo		1.14.5
libreport-filesystem		2.15.2
libselinux	2.5	3.4
libsepol	2.5	3.4
libsigsegv		2.13
libsmartcols		2.37.4
libsolv		0.7.22
libssh2	1.4.3	
libstdc++	7.3.1	11.4.1

<b>Package</b>	<b>AL2 Container</b>	<b>AL2023 Container</b>
libtasn1	4.10	4.19.0
libunistring	0.9.3	0.9.10
libuuid	2.30.2	2.37.4
libverto	0.2.5	0.3.2
libxcrypt		4.4.33
libxml2	2.9.1	2.10.4
libyaml		0.2.5
libzstd		1.5.5
lua	5.1.4	
lua-libs		5.4.4
lz4-libs		1.9.4
mpfr		4.1.0
ncurses	6.0	
ncurses-base	6.0	6.2
ncurses-libs	6.0	6.2
npth		1.6
nspr	4.35.0	
nss	3.90.0	
nss-pem	1.0.3	
nss-softokn	3.90.0	

Package	AL2 Container	AL2023 Container
nss-softokn-freebl	3.90.0	
nss-sysinit	3.90.0	
nss-tools	3.90.0	
nss-util	3.90.0	
openldap	2.4.44	
openssl-libs	1.0.2k	3.0.8
p11-kit	0.23.22	0.24.1
p11-kit-trust	0.23.22	0.24.1
<u>pcre</u>	8.32	
pcre2		10.40
pcre2-syntax		10.40
pinentry	0.8.1	
popt	1.13	1.18
pth	2.0.7	
publicsuffix-list-dafsa	20240208	20240212
pygpgme	0.3	
pyliblzma	0.5.3	
<u>python</u>	2.7.18	
python2-rpm	4.11.3	
python3		3.9.16

<b>Package</b>	<b>AL2 Container</b>	<b>AL2023 Container</b>
python3-dnf		4.14.0
python3-gpg		1.15.1
python3-hawkey		0.69.0
python3-libcomps		0.1.20
python3-libdnf		0.69.0
python3-libs		3.9.16
python3-pip-wheel		21.3.1
python3-rpm		4.16.1.3
python3-setuptools-wheel		59.6.0
python-iniparse	0.4	
python-libs	2.7.18	
python-pycurl	7.19.0	
python-urlgrabber	3.10	
pyxattr	0.5.1	
readline	6.2	8.1
rpm	4.11.3	4.16.1.3
rpm-build-libs	4.11.3	4.16.1.3
rpm-libs	4.11.3	4.16.1.3
rpm-sign-libs		4.16.1.3
sed	4.2.2	4.8

<b>Package</b>	<b>AL2 Container</b>	<b>AL2023 Container</b>
setup	2.8.71	2.13.7
shared-mime-info	1.8	
sqlite	3.7.17	
sqlite-libs		3.40.0
system-release	2	2023.4.20240513
tzdata	2024a	2024a
vim-data	9.0.2153	
vim-minimal	9.0.2153	
xz-libs	5.2.2	5.2.5
yum	3.4.3	4.14.0
yum-metadata-parser	1.1.4	
yum-plugin-ovl	1.1.31	
yum-plugin-priorities	1.1.31	
zlib	1.2.7	1.2.11

# Comparing AL1 and AL2023

The following topics describe key differences between AL1 and AL2023 that aren't already covered by the [comparison with AL2](#).

## Note

AL1 reached its end-of-life (EOL) on December 31, 2023 and will not receive any security updates or bug fixes starting January 1, 2024. For more information about AL1 EOL and maintenance support, see the blog post [Update on Amazon Linux AMI end-of-life](#). We recommend that you upgrade applications to AL2023, which includes long-term support until 2028.

## Topics

- [Support for each release](#)
- [systemd replaces upstart as init system](#)
- [Python 2.6 and 2.7 has been replaced with Python 3](#)
- [OpenJDK 8 as oldest JDK](#)
- [AL2023 kernel changes from Amazon Linux 1 \(AL1\)](#)
- [Comparing packages installed on Amazon Linux 1 \(AL1\) and Amazon Linux 2023 AMIs](#)
- [Comparing packages installed on Amazon Linux 1 \(AL1\) and Amazon Linux 2023 Minimal AMIs](#)
- [Comparing packages installed on Amazon Linux 1 \(AL1\) and Amazon Linux 2023 base container images](#)

## Support for each release

For AL2023, we offer five years of support from the release date. AL1 ended standard support as of December 31, 2020 and ended maintenance support as of December 31, 2023.

For more information, see [Release cadence](#).

## systemd replaces upstart as init system

In AL2 upstart was replaced by systemd as the init system. AL2023 also uses systemd as its init system, further adopting new features and functionality of systemd.

## Python 2.6 and 2.7 has been replaced with Python 3

Although AL1 marked Python 2.6 as EOL with the 2018.03 release, the packages were still available in the repositories to install. AL2 shipped with Python 2.7 as the earliest supported Python version, and AL2023 completes the transition to Python 3. No Python 2.x versions are included in the AL2023 repositories.

For more information on Python on Amazon Linux, see [Python in AL2023](#).

## OpenJDK 8 as oldest JDK

AL2023 ships with [Amazon Corretto](#) as the default (and only) Java Development Kit (JDK). All Java based packages in AL2023 are built with Amazon Corretto 17.

In AL1, OpenJDK 1.6.0 (`java-1.6.0-openjdk`) went EOL with the first 2018.03 release, and OpenJDK 1.7.0 (`java-1.7.0-openjdk`) went EOL in mid-2020, although both versions were available in the AL1 repositories. The earliest OpenJDK version available in AL2023 is OpenJDK 8, provided by Amazon Corretto 8.

## AL2023 kernel changes from Amazon Linux 1 (AL1)

### Kernel Live Patching

Both AL2023 and AL2 add support for kernel live-patching functionality. This allows you to patch critical and important security vulnerabilities in the Linux kernel without reboot or downtime. For more information, see [Kernel Live Patching on AL2023](#).

### Kernel file system support

There have been several changes in the file systems that the kernel in AL1 will support mounting, along with changes in the partitioning schemes that the kernel will parse.

<b>CONFIG option</b>	<b>AL1/4.14/x86_64</b>	<b>AL2023/6.1/aarch64</b>	<b>AL2023/6.1/x86_64</b>
<u><a href="#">CONFIG_AFS_FS</a></u>	m	n	n
<u><a href="#">CONFIG_AF_RXRPC</a></u>	m	n	n
<u><a href="#">CONFIG_BS_D_DISKLABEL</a></u>	y	n	n
<u><a href="#">CONFIG_CRAMFS</a></u>	m	n	n
<u><a href="#">CONFIG_CRAMFS_BLOCKDEV</a></u>	N/A	N/A	N/A
<u><a href="#">CONFIG_DM_CLONE</a></u>	N/A	n	n
<u><a href="#">CONFIG_DM_ERA</a></u>	n	n	n
<u><a href="#">CONFIG_DM_INTEGRITY</a></u>	m	m	m
<u><a href="#">CONFIG_DM_LOG_WRITES</a></u>	n	m	m
<u><a href="#">CONFIG_DM_SWITCH</a></u>	n	n	n
<u><a href="#">CONFIG_DM_VERITY</a></u>	n	n	n
<u><a href="#">CONFIG_ECRYPT_FS</a></u>	m	n	n
<u><a href="#">CONFIG_EXFAT_FS</a></u>	N/A	m	m
<u><a href="#">CONFIG_EXT2_FS</a></u>	m	n	n
<u><a href="#">CONFIG_EXT3_FS</a></u>	m	n	n
<u><a href="#">CONFIG_GFS2_FS</a></u>	n	n	n

CONFIG option	AL1/4.14/x86_64	AL2023/6.1/aarch64	AL2023/6.1/x86_64
<u><a href="#">CONFIG_HF_SPLUS_FS</a></u>	m	n	n
<u><a href="#">CONFIG_HFS_FS</a></u>	m	n	n
<u><a href="#">CONFIG_JFS_FS</a></u>	m	n	n
<u><a href="#">CONFIG_LD_M_PARTITION</a></u>	y	n	n
<u><a href="#">CONFIG_MAC_PARTITION</a></u>	y	n	n
<u><a href="#">CONFIG_NFS_V2</a></u>	m	n	n
<u><a href="#">CONFIG_NTFS_FS</a></u>	m	n	n
<u><a href="#">CONFIG_ROMFS_FS</a></u>	m	n	n
<u><a href="#">CONFIG_SO_LARIS_X86_PARTITION</a></u>	y	n	n
<u><a href="#">CONFIG_SQ_UASHFS_ZSTD</a></u>	y	y	y
<u><a href="#">CONFIG_SU_N_PARTITION</a></u>	y	n	n

## Security focused kernel config changes

CONFIG option	AL1/4.14/x86_64	AL2023/6.1/aarch64	AL2023/6.1/x86_64
<u><a href="#">CONFIG_BUG_ON_DATA_CORRUPTION</a></u>	y	y	y

<b>CONFIG option</b>	<b>AL1/4.14/x86_64</b>	<b>AL2023/6.1/aarch64</b>	<b>AL2023/6.1/x86_64</b>
<u><a href="#">CONFIG_DEFECTIVE_MMA_P_MIN_ADDR</a></u>	4096	65536	65536
<u><a href="#">CONFIG_DEVMEM</a></u>	y	n	n
<u><a href="#">CONFIG_DEVPORT</a></u>	y	n	n
<u><a href="#">CONFIG_FORTIFY_SOURCE</a></u>	y	y	y
<u><a href="#">CONFIG_HARDENED_UNRECOVERABLE_FAULTS</a></u>	N/A	N/A	N/A
<u><a href="#">CONFIG_INJECT_ON_ALL_CODE_DEFAULT_ON</a></u>	N/A	n	n
<u><a href="#">CONFIG_INJECT_ON_FREQUENT_CODE_DEFAULT_ON</a></u>	N/A	n	n
<u><a href="#">CONFIG_IOMMU_DEFAULT_STRICT</a></u>	N/A	n	n
<u><a href="#">CONFIG_LDISC_AUTOLOAD</a></u>	y	n	n
<u><a href="#">CONFIG_SCATTERED_CORE</a></u>	N/A	N/A	y
<u><a href="#">CONFIG_SCATTERED_STACK_END_CHECK</a></u>	y	y	y

CONFIG option	AL1/4.14/x86_64	AL2023/6.1/aarch64	AL2023/6.1/x86_64
<a href="#"><u>CONFIG_SE_CURITY_DM_ESG_RESTRICT</u></a>	n	y	y
<a href="#"><u>CONFIG_SE_CURITY_SE_LINUX_DISABLE</u></a>	y	n	n
<a href="#"><u>CONFIG_SHUFFLE_PAG_E_ALLOCATOR</u></a>	N/A	y	y
<a href="#"><u>CONFIG_SLAB_FREELIST_ST_HARDENED</u></a>	y	y	y
<a href="#"><u>CONFIG_SLAB_FREELIST_ST_RANDOM</u></a>	n	y	y

## Other kernel configuration changes

CONFIG option	AL1/4.14/x86_64	AL2023/6.1/aarch64	AL2023/6.1/x86_64
<a href="#"><u>CONFIG_HZ</u></a>	250	100	100
<a href="#"><u>CONFIG_NR_CPUS</u></a>	8192	512	512
<a href="#"><u>CONFIG_PARITY_NIC_ON_OOPS</u></a>	n	y	y
<a href="#"><u>CONFIG_PARITY_NIC_ON_OO_PS_VALUE</u></a>	0	1	1

CONFIG option	AL1/4.14/x86_64	AL2023/6.1/aarch64	AL2023/6.1/x86_64
<a href="#"><u>CONFIG_PPP</u></a>	m	n	n
<a href="#"><u>CONFIG_SLIP</u></a>	m	n	n
<a href="#"><u>CONFIG_XEN_PV</u></a>	y	N/A	n

## Comparing packages installed on Amazon Linux 1 (AL1) and Amazon Linux 2023 AMIs

A comparison of the RPMs present on the AL1 and AL2023 standard AMIs.

Package	AL1 AMI	AL2023 AMI
acl	2.2.49	2.3.1
acpid	2.0.19	2.0.32
alsa-lib	1.0.22	
alternatives		1.15
amazon-chrony-config		4.3
<a href="#"><u>amazon-ec2-net-utils</u></a>		2.4.1
amazon-linux-repo-s3		2023.4.20240513
<a href="#"><u>amazon-linux-sb-keys</u></a>		2023.1
amazon-rpm-config		228
amazon-ssm-agent	3.2.2222.0	3.3.380.0
at	3.1.10	3.1.23
attr	2.4.46	2.5.1

Package	AL1 AMI	AL2023 AMI
audit	2.6.5	3.0.6
audit-libs	2.6.5	3.0.6
authconfig	6.2.8	
aws-amitools-ec2	1.5.13	
aws-cfn-bootstrap	1.4	2.0
aws-cli	1.18.107	
awscli-2		2.15.30
basesystem	10.0	11
bash	4.2.46	5.2.15
bash-completion		2.11
bc	1.06.95	1.07.1
bind-libs	9.8.2	9.16.48
bind-license		9.16.48
bind-utils	9.8.2	9.16.48
<u>binutils</u>	2.27	2.39
boost-filesystem		1.75.0
boost-system		1.75.0
boost-thread		1.75.0
bzip2	1.0.6	1.0.8
bzip2-libs	1.0.6	1.0.8

Package	AL1 AMI	AL2023 AMI
ca-certificates	2023.2.62	2023.2.64
c-ares		1.19.0
checkpolicy	2.1.10	3.4
chkconfig	1.3.49.3	1.15
chrony		4.3
cloud-disk-utils	0.27	
cloud-init	0.7.6	22.2.2
cloud-init-cfg-ec2		22.2.2
cloud-utils-growpart		0.31
copy-jdk-configs	3.3	
coreutils	8.22	8.32
coreutils-common		8.32
cpio	2.10	2.13
cracklib	2.8.16	2.9.6
cracklib-dicts	2.8.16	2.9.6
<u>cronie</u>	1.4.4	
cronie-anacron	1.4.4	
crontabs	1.10	1.11
crypto-policies		20220428
crypto-policies-scripts		20220428

Package	AL1 AMI	AL2023 AMI
cryptsetup	1.6.7	2.6.1
cryptsetup-libs	1.6.7	2.6.1
<a href="#"><u>curl</u></a>	7.61.1	
<a href="#"><u>curl-minimal</u></a>		8.5.0
cyrus-sasl	2.1.23	
cyrus-sasl-lib	2.1.23	2.1.27
cyrus-sasl-plain	2.1.23	2.1.27
dash	0.5.5.1	
db4	4.7.25	
db4-utils	4.7.25	
dbus	1.6.12	1.12.28
dbus-broker		32
dbus-common		1.12.28
dbus-libs	1.6.12	1.12.28
dejavu-fonts-common	2.33	
dejavu-sans-fonts	2.33	
dejavu-serif-fonts	2.33	
device-mapper	1.02.135	1.02.185
device-mapper-event	1.02.135	
device-mapper-event-libs	1.02.135	

<b>Package</b>	<b>AL1 AMI</b>	<b>AL2023 AMI</b>
device-mapper-libs	1.02.135	1.02.185
device-mapper-persistent-data	0.6.3	
dhclient	4.1.1	
dhcp-common	4.1.1	
diffutils	3.3	3.8
dmraid	1.0.0.rc16	
dmraid-events	1.0.0.rc16	
dnf		4.14.0
dnf-data		4.14.0
dnf-plugin-release-notification		1.2
dnf-plugins-core		4.3.0
dnf-plugin-support-info		1.2
dnf-utils		4.3.0
dosfstools		4.2
dracut	004	055
dracut-config-ec2		3.0
dracut-config-generic		055

<b>Package</b>	<b>AL1 AMI</b>	<b>AL2023 AMI</b>
dracut-modules-growroot	0.20	
dump	0.4	
dwz		0.14
dyninst		10.2.1
e2fsprogs	1.43.5	1.46.5
e2fsprogs-libs	1.43.5	1.46.5
ec2-hibernate-agent	1.0.0	1.0.8
ec2-instance-connect		1.1
ec2-instance-connect-selinux		1.1
ec2-net-utils	0.7	
ec2-utils	0.7	2.2.0
ed	1.1	1.14.2
efi-filesystem		5
efi-srpm-macros		5
efivar		38
efivar-libs		38
elfutils-debuginfod-client		0.188
elfutils-default-ama-scope		0.188

<b>Package</b>	<b>AL1 AMI</b>	<b>AL2023 AMI</b>
elfutils-libelf	0.168	0.188
elfutils-libs		0.188
epel-release	6	
ethtool	3.15	5.15
expat	2.1.0	2.5.0
file	5.37	5.39
file-libs	5.37	5.39
filesystem	2.4.30	3.14
findutils	4.4.2	4.8.0
fipscheck	1.3.1	
fipscheck-lib	1.3.1	
fontconfig	2.8.0	
fontpackages-file system	1.41	
fonts-srpm-macros		2.0.5
freetype	2.3.11	
fstrm		0.6.1
fuse-libs	2.9.4	2.9.9
gawk	3.1.7	5.1.0
gdbm	1.8.0	
gdbm-libs		1.19

Package	AL1 AMI	AL2023 AMI
gdisk	0.8.10	1.0.8
generic-logos	17.0.0	
get_reference_source	1.2	
gettext		0.21
gettext-libs		0.21
ghc-srpm-macros		1.5.0
giflib	4.1.6	
glib2	2.36.3	2.74.7
glibc	2.17	2.34
glibc-all-langpacks		2.34
glibc-common	2.17	2.34
glibc-gconv-extra		2.34
glibc-locale-source		2.34
gmp	6.0.0	6.2.1
<a href="#"><u>gnupg2</u></a>	2.0.28	
<a href="#"><u>gnupg2-minimal</u></a>		2.3.7
gnutls		3.8.0
go-srpm-macros		3.2.0
gpgme	1.4.3	1.15.1
gpm-libs	1.20.6	1.20.7

Package	AL1 AMI	AL2023 AMI
grep	2.20	3.8
groff	1.22.2	
groff-base	1.22.2	1.22.4
grub	0.97	
grub2-common		2.06
grub2-efi-x64-ec2		2.06
grub2-pc-modules		2.06
grub2-tools		2.06
grub2-tools-minimal		2.06
grubby	7.0.15	8.40
gssproxy		0.8.4
gzip	1.5	1.12
hesiod	3.1.0	
hibagent	1.0.0	
hmaccalc	0.9.12	
hostname		3.23
hunspell		1.7.0
hunspell-en		0.20140811.1
hunspell-en-GB		0.20140811.1
hunspell-en-US		0.20140811.1

Package	AL1 AMI	AL2023 AMI
hunspell-filesystem		1.7.0
hwdata	0.233	0.353
info	5.1	6.7
inih		49
initscripts	9.03.58	10.09
iproute	4.4.0	5.10.0
iptables	1.4.21	
iputils	20121221	20210202
irqbalance	1.5.0	1.9.0
jansson		2.14
<a href="#"><u>java-1.7.0-openjdk</u></a>	1.7.0.321	
javapackages-tools	0.9.1	
jitterentropy		3.4.1
jpackage-utils	1.7.5	
jq		1.7.1
json-c		0.14
kbd	1.15	2.4.0
kbd-misc	1.15	2.4.0
kernel	4.14.336	6.1.90
kernel-livepatch-r epo-s3		2023.4.20240513

<b>Package</b>	<b>AL1 AMI</b>	<b>AL2023 AMI</b>
kernel-srpm-macros		1.0
kernel-tools	4.14.336	6.1.90
keyutils	1.5.8	1.6.3
keyutils-libs	1.5.8	1.6.3
kmod	14	29
kmod-libs	14	29
kpartx	0.4.9	
kpatch-runtime		0.9.7
krb5-libs	1.15.1	1.21
lcms2	2.6	
less	436	608
libacl	2.2.49	2.3.1
libaio	0.3.109	0.3.111
libarchive		3.5.3
libargon2		20171227
libassuan	2.0.3	2.5.5
libattr	2.4.46	2.5.1
libbasicobjects		0.1.1
libblkid	2.23.2	2.37.4
libcap	2.16	2.48

Package	AL1 AMI	AL2023 AMI
libcap54	2.54	
libcap-ng	0.7.5	0.8.2
libcbor		0.7.0
libcgroup	0.40.rc1	
libcollection		0.7.0
libcom_err	1.43.5	1.46.5
libcomps		0.1.20
libconfig		1.7.2
<a href="#"><u>libcurl</u></a>	7.61.1	
<a href="#"><u>libcurl-minimal</u></a>		8.5.0
<a href="#"><u>libdb</u></a>		5.3.28
libdhash		0.5.0
libdnf		0.69.0
libeconf		0.4.0
libedit	2.11	3.1
libev		4.33
libevent	2.0.21	2.1.12
libfdisk		2.37.4
libffi	3.0.13	3.4.4
libfido2		1.10.0

<b>Package</b>	<b>AL1 AMI</b>	<b>AL2023 AMI</b>
libfontenc	1.0.5	
libgcc		11.4.1
libgcc72	7.2.1	
libgcrypt	1.5.3	1.10.2
libgomp		11.4.1
libgpg-error	1.11	1.42
libgssglue	0.1	
libibverbs		48.0
libICE	1.0.6	
libicu	50.2	
libidn	1.18	
libidn2	2.3.0	2.3.2
libini_config		1.3.1
libjpeg-turbo	1.2.90	
libkapi		1.4.0
libkapi-hmaccalc		1.4.0
libldb		2.6.2
libmaxminddb		1.5.2
libmetalink		0.1.3
libmnl	1.0.3	1.0.4

<b>Package</b>	<b>AL1 AMI</b>	<b>AL2023 AMI</b>
libmodulemd		2.13.0
libmount	2.23.2	2.37.4
libnetfilter_conntrack	1.0.4	
libnfsidmap	0.25	2.5.4
libnghttp2	1.33.0	1.59.0
libnih	1.0.1	
libnl	1.1.4	
libnl3		3.5.0
libpath_utils		0.2.1
libpcap		1.10.1
libpipeline	1.2.3	1.5.3
libpkgconf		1.8.0
libpng	1.2.49	
libpsl	0.6.2	0.21.1
libpwquality	1.2.3	1.4.4
libref_array		0.1.5
librepo		1.14.5
libreport-filesystem		2.15.2
libseccomp		2.5.3

<b>Package</b>	<b>AL1 AMI</b>	<b>AL2023 AMI</b>
libselinux	2.1.10	3.4
libselinux-utils	2.1.10	3.4
libsemanage	2.1.6	3.4
libsepol	2.1.7	3.4
libsigsegv		2.13
libSM	1.2.1	
libsmartcols	2.23.2	2.37.4
libsolv		0.7.22
libss	1.43.5	1.46.5
libssh2	1.4.2	
libsss_certmap		2.9.4
libsss_idmap		2.9.4
libsss_nss_idmap		2.9.4
libsss_sudo		2.9.4
libstdc++		11.4.1
libstdc++72	7.2.1	
libstoragemgmt		1.9.4
libsysfs	2.1.0	
libtalloc		2.3.4
libtasn1	2.3	4.19.0

<b>Package</b>	<b>AL1 AMI</b>	<b>AL2023 AMI</b>
libtdb		1.4.7
libevent		0.13.0
libtextstyle		0.21
libtirpc	0.2.4	1.3.3
libudev	173	
libunistring	0.9.3	0.9.10
libuser	0.60	0.63
libutempter	1.1.5	1.2.1
libuuid	2.23.2	2.37.4
libuv		1.47.0
libverto	0.2.5	0.3.2
libverto-libev		0.3.2
libX11	1.6.0	
libX11-common	1.6.0	
libXau	1.0.6	
libxcb	1.11	
libXcomposite	0.4.3	
libXcrypt		4.4.33
libXext	1.3.2	
libXfont	1.4.5	

Package	AL1 AMI	AL2023 AMI
libXi	1.7.2	
libxml2	2.9.1	2.10.4
libxml2-python27	2.9.1	
libXrender	0.9.8	
libxslt	1.1.28	
libXtst	1.2.2	
libyaml	0.1.6	0.2.5
libzstd		1.5.5
lm_sensors-libs		3.6.0
lmbdb-libs		0.9.29
<a href="#"><u>log4j-cve-2021-442_28-hotpatch</u></a>	1.3	
logrotate	3.7.8	3.20.1
lsof	4.82	4.94.0
lua	5.1.4	
lua-libs		5.4.4
lua-srpm-macros		1
lvm2	2.02.166	
lvm2-libs	2.02.166	
lz4-libs		1.9.4
mailcap	2.1.31	

<b>Package</b>	<b>AL1 AMI</b>	<b>AL2023 AMI</b>
make	3.82	
man-db	2.6.3	2.9.3
man-pages	4.10	5.10
mdadm	3.2.6	
microcode_ctl	2.1	2.1
mingetty	1.08	
mpfr		4.1.0
nano	2.5.3	5.8
nc	1.84	
ncurses	5.7	6.2
ncurses-base	5.7	6.2
ncurses-libs	5.7	6.2
nettle		3.8
net-tools	1.60	2.0
newt	0.52.11	0.52.21
newt-python27	0.52.11	
nfs-utils	1.3.0	2.5.4
npth		1.6
nspr	4.25.0	4.35.0
nss	3.53.1	3.90.0

Package	AL1 AMI	AL2023 AMI
nss-pem	1.0.3	
nss-softokn	3.53.1	3.90.0
nss-softokn-freebl	3.53.1	3.90.0
nss-sysinit	3.53.1	3.90.0
nss-tools	3.53.1	
nss-util	3.53.1	3.90.0
ntp	4.2.8p15	
ntpdate	4.2.8p15	
ntsysv	1.3.49.3	1.15
numactl	2.0.7	
numactl-libs		2.0.14
ocaml-srpm-macros		6
oniguruma		6.9.7.1
openblas-srpm-macros		2
openldap	2.4.40	2.4.57
openssh	7.4p1	8.7p1
openssh-clients	7.4p1	8.7p1
openssh-server	7.4p1	8.7p1
openssl	1.0.2k	3.0.8
openssl-libs		3.0.8

Package	AL1 AMI	AL2023 AMI
openssl-pkcs11		0.4.12
os-prober		1.77
p11-kit	0.18.5	0.24.1
p11-kit-trust	0.18.5	0.24.1
package-notes-srpm-macros		0.4
pam	1.1.8	1.5.1
pam_ccreds	10	
pam_krb5	2.3.11	
pam_passwdqc	1.0.5	
parted	2.1	3.4
passwd	0.79	0.80
pciutils	3.1.10	3.7.0
pciutils-libs	3.1.10	3.7.0
<u>pcre</u>	8.21	
pcre2		10.40
pcre2-syntax		10.40
<u>perl</u>	5.16.3	
perl-Carp	1.26	1.50
perl-Class-Struct		0.66
perl-constant	1.27	1.33

<b>Package</b>	<b>AL1 AMI</b>	<b>AL2023 AMI</b>
perl-Digest	1.17	
perl-Digest-HMAC	1.03	
perl-Digest-MD5	2.52	
perl-Digest-SHA	5.85	
perl-DynaLoader		1.47
perl-Encode	2.51	3.15
perl-Errno		1.30
perl-Exporter	5.68	5.74
perl-Fcntl		1.13
perl-File-Basename		2.85
perl-File-Path	2.09	2.18
perl-File-stat		1.09
perl-File-Temp	0.23.01	0.231.100
perl-Filter	1.49	
perl-Getopt-Long	2.40	2.52
perl-Getopt-Std		1.12
perl-HTTP-Tiny	0.033	0.078
perl-if		0.60.800
perl-interpreter		5.32.1
perl-IO		1.43

<b>Package</b>	<b>AL1 AMI</b>	<b>AL2023 AMI</b>
perl-IPC-Open3		1.21
perl-libs	5.16.3	5.32.1
perl-macros	5.16.3	
perl-MIME-Base64		3.16
perl-mro		1.23
perl-overload		1.31
perl-overloading		0.02
perl-parent	0.225	0.238
perl-PathTools	3.40	3.78
perl-Pod-Escapes	1.04	1.07
perl-podlators	2.5.1	4.14
perl-Pod-Perldoc	3.20	3.28.01
perl-Pod-Simple	3.28	3.42
perl-Pod-Usage	1.63	2.01
perl-POSIX		1.94
perl-Scalar-List-Utils	1.27	1.56
perl-SelectSaver		1.02
perl-Socket	2.010	2.032
perl-srpm-macros		1
perl-Storable	2.45	3.21

<b>Package</b>	<b>AL1 AMI</b>	<b>AL2023 AMI</b>
perl-sub		1.03
perl-Symbol		1.08
perl-Term-ANSIColor		5.01
perl-Term-Cap		1.17
perl-Text-ParseWords	3.29	3.30
perl-Text-Tabs+Wrap		2021.0726
perl-threads	1.87	
perl-threads-shared	1.43	
perl-Time-HiRes	1.9725	
perl-Time-Local	1.2300	1.300
perl-vars		1.05
pinentry	0.7.6	
pkgconf		1.8.0
pkgconfig	0.27.1	
pkgconf-m4		1.8.0
pkgconf-pkg-config		1.8.0
pm-utils	1.4.1	
policycoreutils	2.1.12	3.4
policycoreutils-py thon-utils		3.4
popt	1.13	1.18

<b>Package</b>	<b>AL1 AMI</b>	<b>AL2023 AMI</b>
procmail	3.22	
procps	3.2.8	
procps-ng		3.3.17
protobuf-c		1.4.1
psacct	6.3.2	6.6.4
psmisc	22.20	23.4
pth	2.0.7	
publicsuffix-list-dafsa		20240212
python27	2.7.18	
python27-babel	0.9.4	
python27-backports	1.0	
python27-backports-ssl_match_hostname	3.4.0.2	
python27-boto	2.48.0	
python27-botocore	1.17.31	
python27-chardet	2.0.1	
python27-colorama	0.4.1	
python27-configobj	4.7.2	
python27-crypto	2.6.1	
python27-daemon	1.5.2	

<b>Package</b>	<b>AL1 AMI</b>	<b>AL2023 AMI</b>
python27-dateutil	2.1	
python27-devel	2.7.18	
python27-docutils	0.11	
python27-ecdsa	0.11	
python27-futures	3.0.3	
python27-imaging	1.1.6	
python27-iniparse	0.3.1	
python27-jinja2	2.7.2	
python27-jmespath	0.9.2	
python27-jsonpatch	1.2	
python27-jsonpointer	1.0	
python27-kitchen	1.1.1	
python27-libs	2.7.18	
python27-lockfile	0.8	
python27-markupsafe	0.11	
python27-paramiko	1.15.1	
python27-pip	9.0.3	
python27-ply	3.4	
python27-pyasn1	0.1.7	
python27-pycurl	7.19.0	

<b>Package</b>	<b>AL1 AMI</b>	<b>AL2023 AMI</b>
python27-pygpgme	0.3	
python27-pyliblzma	0.5.3	
python27-pystache	0.5.3	
python27-pyxattr	0.5.0	
python27-PyYAML	3.10	
python27-requests	1.2.3	
python27-rsa	3.4.1	
python27-setuptools	36.2.7	
python27-simplejson	3.6.5	
python27-six	1.8.0	
python27-urlgrabber	3.10	
python27-urllib3	1.24.3	
python27-virtualenv	15.1.0	
python3		3.9.16
python3-attrs		20.3.0
python3-audit		3.0.6
python3-awscrt		0.19.19
python3-babel		2.9.1
python3-cffi		1.14.5
python3-chardet		4.0.0

<b>Package</b>	<b>AL1 AMI</b>	<b>AL2023 AMI</b>
python3-colorama		0.4.4
python3-configobj		5.0.6
python3-cryptography		36.0.1
python3-daemon		2.3.0
python3-dateutil		2.8.1
python3-dbus		1.2.18
python3-distro		1.5.0
python3-dnf		4.14.0
python3-dnf-plugins-core		4.3.0
python3-docutils		0.16
python3-gpg		1.15.1
python3-hawkey		0.69.0
python3-idna		2.10
python3-jinja2		2.11.3
python3-jmespath		0.10.0
python3-jsonpatch		1.21
python3-jsonpointer		2.0
python3-jsonschema		3.2.0
python3-libcomps		0.1.20
python3-libdnf		0.69.0

Package	AL1 AMI	AL2023 AMI
python3-libs		3.9.16
python3-libselinux		3.4
python3-libsemanage		3.4
python3-libstorage mgmt		1.9.4
python3-lockfile		0.12.2
python3-markupsafe		1.1.1
python3-netifaces		0.10.6
python3-oauthlib		3.0.2
python3-pip-wheel		21.3.1
python3-ply		3.11
python3-policycore utils		3.4
python3-prettytable		0.7.2
python3-prompt-too lkit		3.0.24
python3-pycparser		2.20
python3-pyrsistent		0.17.3
python3-pyserial		3.4
python3-pysocks		1.7.1
python3-pytz		2022.7.1

Package	AL1 AMI	AL2023 AMI
python3-pyyaml		5.4.1
python3-requests		2.25.1
python3-rpm		4.16.1.3
python3-ruamel-yaml		0.16.6
python3-ruamel-yaml- clib		0.1.2
python3-setools		4.4.1
python3-setuptools		59.6.0
python3-setuptools- wheel		59.6.0
python3-six		1.15.0
python3-systemd		235
python3-urllib3		1.25.10
python3-wcwidth		0.2.5
python-chevron		0.13.1
python-srpm-macros		3.9
quota	4.00	4.06
quota-nls	4.00	4.06
readline	6.2	8.1
rmt	0.4	
rng-tools	5	6.14

<b>Package</b>	<b>AL1 AMI</b>	<b>AL2023 AMI</b>
rootfiles	8.1	8.1
rpcbind	0.2.0	1.2.6
rpm	4.11.3	4.16.1.3
rpm-build-libs	4.11.3	4.16.1.3
rpm-libs	4.11.3	4.16.1.3
rpm-plugin-selinux		4.16.1.3
rpm-plugin-systemd-inhibit		4.16.1.3
rpm-python27	4.11.3	
rpm-sign-libs		4.16.1.3
rsync	3.0.6	3.2.6
rsyslog	5.8.10	
ruby	2.0	
ruby20	2.0.0.648	
ruby20-irb	2.0.0.648	
ruby20-libs	2.0.0.648	
rubygem20-bigdecimal	1.2.0	
rubygem20-json	1.8.3	
rubygem20-psych	2.0.0	
rubygem20-rdoc	4.2.2	
rubygems20	2.0.14.1	

<b>Package</b>	<b>AL1 AMI</b>	<b>AL2023 AMI</b>
<code>rust-srpm-macros</code>		21
<code>sbsigntools</code>		0.9.4
<code>screen</code>	4.0.3	4.8.0
<code>sed</code>	4.2.1	4.8
<code>selinux-policy</code>		37.22
<code>selinux-policy-targeted</code>		37.22
<code>sendmail</code>	8.14.4	
<code>setserial</code>	2.17	
<code>setup</code>	2.8.14	2.13.7
<code>sgpio</code>	1.2.0.10	
<code>shadow-utils</code>	4.1.4.2	4.9
<code>shared-mime-info</code>	1.1	
<code>slang</code>	2.2.1	2.3.2
<code>sqlite</code>	3.7.17	
<code>sqlite-libs</code>		3.40.0
<code>sssd-client</code>		2.9.4
<code>sssd-common</code>		2.9.4
<code>sssd-kcm</code>		2.9.4
<code>sssd-nfs-idmap</code>		2.9.4
<code>strace</code>		6.8

<b>Package</b>	<b>AL1 AMI</b>	<b>AL2023 AMI</b>
sudo	1.8.23	1.9.15
sysctl-defaults	1.0	1.0
sysfsutils	2.1.0	
sysstat		12.5.6
systemd		252.16
systemd-libs		252.16
systemd-networkd		252.16
systemd-pam		252.16
systemd-resolved		252.16
systemd-udev		252.16
system-release	2018.03	2023.4.20240513
systemtap-runtime		4.8
sysvinit	2.87	
tar	1.26	1.34
tbb		2020.3
tcp_wrappers	7.6	
tcp_wrappers-libs	7.6	
tcpdump		4.99.1
tcsh		6.24.07
time	1.7	1.9

Package	AL1 AMI	AL2023 AMI
tmpwatch	2.9.16	
traceroute	2.0.14	2.1.3
ttmkfdir	3.0.9	
tzdata	2023c	2024a
tzdata-java	2023c	
udev	173	
unzip	6.0	6.0
update-motd	1.0.1	2.2
<u>upstart</u>	0.6.5	
userspace-rcu		0.12.1
ustr	1.0.4	
util-linux	2.23.2	2.37.4
util-linux-core		2.37.4
vim-common	9.0.2120	9.0.2153
vim-data	9.0.2120	9.0.2153
vim-enhanced	9.0.2120	9.0.2153
vim-filesystem	9.0.2120	9.0.2153
vim-minimal	9.0.2120	9.0.2153
wget	1.18	1.21.3
which	2.19	2.21

Package	AL1 AMI	AL2023 AMI
words	3.0	3.0
xfsdump		3.1.11
xsfsprogs		5.18.0
xorg-x11-fonts-Type1	7.2	
xorg-x11-font-utils	7.2	
xxd	9.0.2120	9.0.2153
xxhash-libs		0.8.0
xz	5.2.2	5.2.5
xz-libs	5.2.2	5.2.5
yum	3.4.3	4.14.0
yum-metadata-parser	1.1.4	
yum-plugin-priorities	1.1.31	
yum-plugin-upgrade-helper	1.1.31	
yum-utils	1.1.31	
zip	3.0	3.0
zlib	1.2.8	1.2.11
zram-generator		1.1.2
zram-generator-defaults		1.1.2

Package	AL1 AMI	AL2023 AMI
zstd		1.5.5

## Comparing packages installed on Amazon Linux 1 (AL1) and Amazon Linux 2023 Minimal AMIs

A comparison of the RPMs present on the AL1 and AL2023 Minimal AMIs.

Package	AL1 Minimal	AL2023 Minimal
acpid	2.0.19	
alternatives		1.15
amazon-chrony-config		4.3
<a href="#"><u>amazon-ec2-net-utils</u></a>		2.4.1
amazon-linux-repo-s3		2023.4.20240513
<a href="#"><u>amazon-linux-sb-keys</u></a>		2023.1
audit	2.6.5	3.0.6
audit-libs	2.6.5	3.0.6
authconfig	6.2.8	
awscli-2		2.15.30
basesystem	10.0	11
bash	4.2.46	5.2.15
<a href="#"><u>binutils</u></a>	2.27	
bzip2	1.0.6	

Package	AL1 Minimal	AL2023 Minimal
bzip2-libs	1.0.6	1.0.8
ca-certificates	2023.2.62	2023.2.64
checkpolicy	2.1.10	3.4
chkconfig	1.3.49.3	
chrony		4.3
cloud-disk-utils	0.27	
cloud-init	0.7.6	22.2.2
cloud-init-cfg-ec2		22.2.2
cloud-utils-growpart		0.31
coreutils	8.22	8.32
coreutils-common		8.32
cpio	2.10	2.13
cracklib	2.8.16	2.9.6
cracklib-dicts	2.8.16	2.9.6
<u>cronie</u>	1.4.4	
cronie-anacron	1.4.4	
crontabs	1.10	
crypto-policies		20220428
cryptsetup-libs		2.6.1
<u>curl</u>	7.61.1	

Package	AL1 Minimal	AL2023 Minimal
<a href="#"><u>curl-minimal</u></a>		8.5.0
cyrus-sasl	2.1.23	
cyrus-sasl-lib	2.1.23	2.1.27
dash	0.5.5.1	
db4	4.7.25	
db4-utils	4.7.25	
dbus		1.12.28
dbus-broker		32
dbus-common		1.12.28
dbus-libs	1.6.12	1.12.28
device-mapper		1.02.185
device-mapper-libs		1.02.185
dhclient	4.1.1	
dhcp-common	4.1.1	
diffutils	3.3	3.8
dnf		4.14.0
dnf-data		4.14.0
dnf-plugin-release-notification		1.2
dnf-plugins-core		4.3.0

<b>Package</b>	<b>AL1 Minimal</b>	<b>AL2023 Minimal</b>
dnf-plugin-support-info		1.2
dracut	004	055
dracut-config-ec2		3.0
dracut-config-generic		055
dracut-modules-growroot	0.20	
e2fsprogs	1.43.5	1.46.5
e2fsprogs-libs	1.43.5	1.46.5
ec2-utils	0.7	2.2.0
ed	1.1	
efi-filesystem		5
efivar		38
efivar-libs		38
elfutils-default-ama-scope		0.188
elfutils-libelf	0.168	0.188
elfutils-libs		0.188
ethtool	3.15	
expat	2.1.0	2.5.0
file	5.37	5.39

<b>Package</b>	<b>AL1 Minimal</b>	<b>AL2023 Minimal</b>
file-libs	5.37	5.39
filesystem	2.4.30	3.14
findutils	4.4.2	4.8.0
fipscheck	1.3.1	
fipscheck-lib	1.3.1	
fuse-libs	2.9.4	2.9.9
gawk	3.1.7	5.1.0
gdbm	1.8.0	
gdbm-libs		1.19
gdisk	0.8.10	1.0.8
generic-logos	17.0.0	
get_reference_source	1.2	
gettext		0.21
gettext-libs		0.21
glib2	2.36.3	2.74.7
glibc	2.17	2.34
glibc-all-langpacks		2.34
glibc-common	2.17	2.34
glibc-locale-source		2.34
gmp	6.0.0	6.2.1

<b>Package</b>	<b>AL1 Minimal</b>	<b>AL2023 Minimal</b>
<a href="#"><u>gnupg2</u></a>	2.0.28	
<a href="#"><u>gnupg2-minimal</u></a>		2.3.7
<a href="#"><u>gnutls</u></a>		3.8.0
gpgme	1.4.3	1.15.1
grep	2.20	3.8
groff	1.22.2	
<a href="#"><u>groff-base</u></a>	1.22.2	1.22.4
grub	0.97	
<a href="#"><u>grub2-common</u></a>		2.06
<a href="#"><u>grub2-efi-x64-ec2</u></a>		2.06
<a href="#"><u>grub2-pc-modules</u></a>		2.06
<a href="#"><u>grub2-tools</u></a>		2.06
<a href="#"><u>grub2-tools-minimal</u></a>		2.06
grubby	7.0.15	8.40
<a href="#"><u>gzip</u></a>	1.5	1.12
hesiod	3.1.0	
<a href="#"><u>hmaccalc</u></a>	0.9.12	
hostname		3.23
<a href="#"><u>hwdata</u></a>	0.233	0.353
info	5.1	

<b>Package</b>	<b>AL1 Minimal</b>	<b>AL2023 Minimal</b>
inith		49
initscripts	9.03.58	10.09
iproute	4.4.0	5.10.0
iptables	1.4.21	
iputils	20121221	20210202
irqbalance		1.9.0
jansson		2.14
jitterentropy		3.4.1
jq		1.7.1
json-c		0.14
kbd	1.15	2.4.0
kbd-misc	1.15	2.4.0
kernel	4.14.336	6.1.90
kernel-livepatch-r epo-s3		2023.4.20240513
keyutils-libs	1.5.8	1.6.3
kmod	14	29
kmod-libs	14	29
krb5-libs	1.15.1	1.21
less	436	608
libacl	2.2.49	2.3.1

<b>Package</b>	<b>AL1 Minimal</b>	<b>AL2023 Minimal</b>
libarchive		3.5.3
libargon2		20171227
libassuan	2.0.3	2.5.5
libattr	2.4.46	2.5.1
libblkid	2.23.2	2.37.4
libcap	2.16	2.48
libcap54	2.54	
libcap-ng	0.7.5	0.8.2
libcbor		0.7.0
libcgroup	0.40.rc1	
libcom_err	1.43.5	1.46.5
libcomps		0.1.20
<a href="#"><u>curl</u></a>	7.61.1	
<a href="#"><u>curl-minimal</u></a>		8.5.0
<a href="#"><u>libdb</u></a>		5.3.28
libdnf		0.69.0
libeconf		0.4.0
libedit	2.11	3.1
libfdisk		2.37.4
libffi	3.0.13	3.4.4

<b>Package</b>	<b>AL1 Minimal</b>	<b>AL2023 Minimal</b>
libfido2		1.10.0
libgcc		11.4.1
libgcc72	7.2.1	
libgcrypt	1.5.3	1.10.2
libgomp		11.4.1
libgpg-error	1.11	1.42
libicu	50.2	
libidn	1.18	
libidn2	2.3.0	2.3.2
libkapi		1.4.0
libkapi-hmaccalc		1.4.0
libmn1	1.0.3	1.0.4
libmodulemd		2.13.0
libmount	2.23.2	2.37.4
libnetfilter_conntrack	1.0.4	
libnfnetlink	1.0.1	
libnghhttp2	1.33.0	1.59.0
libnih	1.0.1	
libpipeline		1.5.3
libpsl	0.6.2	0.21.1

<b>Package</b>	<b>AL1 Minimal</b>	<b>AL2023 Minimal</b>
libpwquality	1.2.3	1.4.4
librepo		1.14.5
libreport-filesystem		2.15.2
libseccomp		2.5.3
libselinux	2.1.10	3.4
libselinux-utils	2.1.10	3.4
libsemanage	2.1.6	3.4
libsepolicy	2.1.7	3.4
libsigsegv		2.13
libsmartcols	2.23.2	2.37.4
libsolv		0.7.22
libss	1.43.5	1.46.5
libssh2	1.4.2	
libstdc++		11.4.1
libstdc++72	7.2.1	
libsysfs	2.1.0	
libtasn1	2.3	4.19.0
libtextstyle		0.21
libudev	173	
libunistring	0.9.3	0.9.10

<b>Package</b>	<b>AL1 Minimal</b>	<b>AL2023 Minimal</b>
libuser	0.60	0.63
libutempter	1.1.5	1.2.1
libuuid	2.23.2	2.37.4
libverto	0.2.5	0.3.2
libxcrypt		4.4.33
libxml2	2.9.1	2.10.4
libyaml	0.1.6	0.2.5
libzstd		1.5.5
logrotate	3.7.8	3.20.1
lua	5.1.4	
lua-libs		5.4.4
lz4-libs		1.9.4
make	3.82	
man-db		2.9.3
microcode_ctl	2.1	2.1
mingetty	1.08	
mpfr		4.1.0
ncurses	5.7	6.2
ncurses-base	5.7	6.2
ncurses-libs	5.7	6.2

<b>Package</b>	<b>AL1 Minimal</b>	<b>AL2023 Minimal</b>
nettle		3.8
net-tools	1.60	2.0
newt	0.52.11	
newt-python27	0.52.11	
npth		1.6
nspr	4.25.0	
nss	3.53.1	
nss-pem	1.0.3	
nss-softokn	3.53.1	
nss-softokn-freebl	3.53.1	
nss-sysinit	3.53.1	
nss-tools	3.53.1	
nss-util	3.53.1	
ntp	4.2.8p15	
ntpdate	4.2.8p15	
numactl-libs		2.0.14
oniguruma		6.9.7.1
openldap	2.4.40	2.4.57
openssh	7.4p1	8.7p1
openssh-clients		8.7p1

<b>Package</b>	<b>AL1 Minimal</b>	<b>AL2023 Minimal</b>
openssh-server	7.4p1	8.7p1
openssl	1.0.2k	3.0.8
openssl-libs		3.0.8
openssl-pkcs11		0.4.12
os-prober		1.77
p11-kit	0.18.5	0.24.1
p11-kit-trust	0.18.5	0.24.1
pam	1.1.8	1.5.1
passwd	0.79	0.80
pciutils	3.1.10	3.7.0
pciutils-libs	3.1.10	3.7.0
<u>pcre</u>	8.21	
pcre2		10.40
pcre2-syntax		10.40
pinentry	0.7.6	
pkgconfig	0.27.1	
policycoreutils	2.1.12	3.4
popt	1.13	1.18
procmail	3.22	
procps	3.2.8	

<b>Package</b>	<b>AL1 Minimal</b>	<b>AL2023 Minimal</b>
procps-ng		3.3.17
psmisc	22.20	23.4
pth	2.0.7	
publicsuffix-list-dafsa		20240212
python27	2.7.18	
python27-babel	0.9.4	
python27-backports	1.0	
python27-backports-ssl_match_hostname	3.4.0.2	
python27-chardet	2.0.1	
python27-configobj	4.7.2	
python27-iniparse	0.3.1	
python27-jinja2	2.7.2	
python27-jsonpatch	1.2	
python27-jsonpointer	1.0	
python27-libs	2.7.18	
python27-markupsafe	0.11	
python27-pycurl	7.19.0	
python27-pygments	0.3	
python27-pyliblzma	0.5.3	

<b>Package</b>	<b>AL1 Minimal</b>	<b>AL2023 Minimal</b>
python27-pyxattr	0.5.0	
python27-PyYAML	3.10	
python27-requests	1.2.3	
python27-setuptools	36.2.7	
python27-six	1.8.0	
python27-urlgrabber	3.10	
python27-urllib3	1.24.3	
python3		3.9.16
python3-attrs		20.3.0
python3-audit		3.0.6
python3-awscrt		0.19.19
python3-babel		2.9.1
python3-cffi		1.14.5
python3-chardet		4.0.0
python3-colorama		0.4.4
python3-configobj		5.0.6
python3-cryptography		36.0.1
python3-dateutil		2.8.1
python3-dbus		1.2.18
python3-distro		1.5.0

<b>Package</b>	<b>AL1 Minimal</b>	<b>AL2023 Minimal</b>
python3-dnf		4.14.0
python3-dnf-plugins-core		4.3.0
python3-docutils		0.16
python3-gpg		1.15.1
python3-hawkey		0.69.0
python3-idna		2.10
python3-jinja2		2.11.3
python3-jmespath		0.10.0
python3-jsonpatch		1.21
python3-jsonpointer		2.0
python3-jsonschema		3.2.0
python3-libcomps		0.1.20
python3-libdnf		0.69.0
python3-libs		3.9.16
python3-libselinux		3.4
python3-libsemanage		3.4
python3-markupsafe		1.1.1
python3-netifaces		0.10.6
python3-oauthlib		3.0.2
python3-pip-wheel		21.3.1

<b>Package</b>	<b>AL1 Minimal</b>	<b>AL2023 Minimal</b>
python3-ply		3.11
python3-policycoreutils		3.4
python3-prettytable		0.7.2
python3-prompt-toolkit		3.0.24
python3-pycparser		2.20
python3-pyrsistent		0.17.3
python3-pyserial		3.4
python3-pysocks		1.7.1
python3-pytz		2022.7.1
python3-pyyaml		5.4.1
python3-requests		2.25.1
python3-rpm		4.16.1.3
python3-ruamel-yaml		0.16.6
python3-ruamel-yaml-cli		0.1.2
python3-setuptools		4.4.1
python3-setuptools		59.6.0
python3-setuptools-wheel		59.6.0
python3-six		1.15.0

<b>Package</b>	<b>AL1 Minimal</b>	<b>AL2023 Minimal</b>
python3-systemd		235
python3-urllib3		1.25.10
python3-wcwidth		0.2.5
readline	6.2	8.1
rng-tools		6.14
rootfiles	8.1	8.1
rpm	4.11.3	4.16.1.3
rpm-build-libs	4.11.3	4.16.1.3
rpm-libs	4.11.3	4.16.1.3
rpm-plugin-selinux		4.16.1.3
rpm-plugin-systemd-inhibit		4.16.1.3
rpm-python27	4.11.3	
rpm-sign-libs		4.16.1.3
rsyslog	5.8.10	
sbsigntools		0.9.4
sed	4.2.1	4.8
selinux-policy		37.22
selinux-policy-targeted		37.22
sendmail	8.14.4	

<b>Package</b>	<b>AL1 Minimal</b>	<b>AL2023 Minimal</b>
setserial	2.17	
setup	2.8.14	2.13.7
shadow-utils	4.1.4.2	4.9
shared-mime-info	1.1	
slang	2.2.1	
sqlite	3.7.17	
sqlite-libs		3.40.0
sudo	1.8.23	1.9.15
sysctl-defaults	1.0	1.0
sysfsutils	2.1.0	
systemd		252.16
systemd-libs		252.16
systemd-networkd		252.16
systemd-pam		252.16
systemd-resolved		252.16
systemd-udev		252.16
system-release	2018.03	2023.4.20240513
sysvinit	2.87	
tar	1.26	1.34
tcp_wrappers-libs	7.6	

<b>Package</b>	<b>AL1 Minimal</b>	<b>AL2023 Minimal</b>
tzdata	2023c	2024a
udev	173	
update-motd	1.0.1	2.2
<a href="#"><u>upstart</u></a>	0.6.5	
userspace-rcu		0.12.1
ustr	1.0.4	
util-linux	2.23.2	2.37.4
util-linux-core		2.37.4
vim-data	9.0.2120	9.0.2153
vim-minimal	9.0.2120	9.0.2153
which	2.19	2.21
xfssprogs		5.18.0
xz	5.2.2	5.2.5
xz-libs	5.2.2	5.2.5
yum	3.4.3	4.14.0
yum-metadata-parser	1.1.4	
yum-plugin-priorities	1.1.31	
yum-plugin-upgrade-helper	1.1.31	
zlib	1.2.8	1.2.11

Package	AL1 Minimal	AL2023 Minimal
zram-generator		1.1.2
zram-generator-defaulsts		1.1.2
zstd		1.5.5

## Comparing packages installed on Amazon Linux 1 (AL1) and Amazon Linux 2023 base container images

A comparison of the RPMs present on the AL1 and AL2023 base container images.

Package	AL1 Container	AL2023 Container
alternatives		1.15
amazon-linux-repo-cdn		2023.4.20240513
audit-libs		3.0.6
basesystem	10.0	11
bash	4.2.46	5.2.15
bzip2-libs	1.0.6	1.0.8
ca-certificates	2023.2.62	2023.2.64
chkconfig	1.3.49.3	
coreutils	8.22	
coreutils-single		8.32
crypto-policies		20220428

Package	AL1 Container	AL2023 Container
<a href="#"><u>curl</u></a>	7.61.1	
<a href="#"><u>curl-minimal</u></a>		8.5.0
cyrus-sasl-lib	2.1.23	
db4	4.7.25	
db4-utils	4.7.25	
dnf		4.14.0
dnf-data		4.14.0
elfutils-default-y ama-scope		0.188
elfutils-libelf	0.168	0.188
elfutils-libs		0.188
expat	2.1.0	2.5.0
file-libs	5.37	5.39
filesystem	2.4.30	3.14
gawk	3.1.7	5.1.0
gdbm	1.8.0	
gdbm-libs		1.19
glib2	2.36.3	2.74.7
glibc	2.17	2.34
glibc-common	2.17	2.34

<b>Package</b>	<b>AL1 Container</b>	<b>AL2023 Container</b>
glibc-minimal-lang pack		2.34
gmp	6.0.0	6.2.1
<a href="#">gnupg2</a>	2.0.28	
<a href="#"><u>gnupg2-minimal</u></a>		2.3.7
gpgme	1.4.3	1.15.1
grep	2.20	3.8
gzip	1.5	
info	5.1	
json-c		0.14
keyutils-libs	1.5.8	1.6.3
krb5-libs	1.15.1	1.21
libacl	2.2.49	2.3.1
libarchive		3.5.3
libassuan	2.0.3	2.5.5
libattr	2.4.46	2.5.1
libblkid		2.37.4
libcap	2.16	2.48
libcap-ng		0.8.2
libcom_err	1.43.5	1.46.5
libcomps		0.1.20

Package	AL1 Container	AL2023 Container
<a href="#"><u>libcurl</u></a>	7.61.1	
<a href="#"><u>libcurl-minimal</u></a>		8.5.0
libdnf		0.69.0
libffi	3.0.13	3.4.4
libgcc		11.4.1
libgcc72	7.2.1	
libgcrypt	1.5.3	1.10.2
libgomp		11.4.1
libgpg-error	1.11	1.42
libicu	50.2	
libidn2	2.3.0	2.3.2
libmodulemd		2.13.0
libmount		2.37.4
libnghttp2	1.33.0	1.59.0
libpsl	0.6.2	0.21.1
librepo		1.14.5
libreport-filesystem		2.15.2
libselinux	2.1.10	3.4
libsepol	2.1.7	3.4
libsigsegv		2.13

<b>Package</b>	<b>AL1 Container</b>	<b>AL2023 Container</b>
libsmartcols		2.37.4
libsolv		0.7.22
libssh2	1.4.2	
libstdc++		11.4.1
libstdc++72	7.2.1	
libtasn1	2.3	4.19.0
libunistring	0.9.3	0.9.10
libuuid		2.37.4
libverto	0.2.5	0.3.2
libxcrypt		4.4.33
libxml2	2.9.1	2.10.4
libxml2-python27	2.9.1	
libyaml		0.2.5
libzstd		1.5.5
lua	5.1.4	
lua-libs		5.4.4
lz4-libs		1.9.4
make	3.82	
mpfr		4.1.0
ncurses	5.7	

Package	AL1 Container	AL2023 Container
ncurses-base	5.7	6.2
ncurses-libs	5.7	6.2
npth		1.6
nspr	4.25.0	
nss	3.53.1	
nss-pem	1.0.3	
nss-softokn	3.53.1	
nss-softokn-freebl	3.53.1	
nss-sysinit	3.53.1	
nss-tools	3.53.1	
nss-util	3.53.1	
openldap	2.4.40	
openssl	1.0.2k	
openssl-libs		3.0.8
p11-kit	0.18.5	0.24.1
p11-kit-trust	0.18.5	0.24.1
<u>pcre</u>	8.21	
pcre2		10.40
pcre2-syntax		10.40
pinentry	0.7.6	

<b>Package</b>	<b>AL1 Container</b>	<b>AL2023 Container</b>
pkgconfig	0.27.1	
popt	1.13	1.18
pth	2.0.7	
publicsuffix-list-dafsa		20240212
python27	2.7.18	
python27-chardet	2.0.1	
python27-iniparse	0.3.1	
python27-kitchen	1.1.1	
python27-libs	2.7.18	
python27-pycurl	7.19.0	
python27-pygpme	0.3	
python27-pyliblzma	0.5.3	
python27-pyxattr	0.5.0	
python27-urlgrabber	3.10	
python3		3.9.16
python3-dnf		4.14.0
python3-gpg		1.15.1
python3-hawkey		0.69.0
python3-libcomps		0.1.20
python3-libdnf		0.69.0

<b>Package</b>	<b>AL1 Container</b>	<b>AL2023 Container</b>
python3-libs		3.9.16
python3-pip-wheel		21.3.1
python3-rpm		4.16.1.3
python3-setuptools-wheel		59.6.0
readline	6.2	8.1
rpm	4.11.3	4.16.1.3
rpm-build-libs	4.11.3	4.16.1.3
rpm-libs	4.11.3	4.16.1.3
rpm-python27	4.11.3	
rpm-sign-libs		4.16.1.3
sed	4.2.1	4.8
setup	2.8.14	2.13.7
shared-mime-info	1.1	
sqlite	3.7.17	
sqlite-libs		3.40.0
sysctl-defaults	1.0	
system-release	2018.03	2023.4.20240513
tar	1.26	
tzdata	2023c	2024a
xz-libs	5.2.2	5.2.5

Package	AL1 Container	AL2023 Container
yum	3.4.3	4.14.0
yum-metadata-parser	1.1.4	
yum-plugin-ovl	1.1.31	
yum-plugin-priorities	1.1.31	
yum-utils	1.1.31	
zlib	1.2.8	1.2.11

# AL2023 system requirements

This section describes the system requirements for using AL2023.

## Topics

- [CPU requirements for running AL2023](#)
- [Memory \(RAM\) requirements for running AL2023](#)

## CPU requirements for running AL2023

To run any AL2023 code, the processor used needs to meet certain minimum requirements. Attempts to run AL2023 on CPUs that do not meet these requirements might result in illegal instruction errors very early in code execution.

The minimum requirements apply to [AL2023 on Amazon EC2](#), [AL2023 in containers](#), and [AL2023 outside Amazon EC2](#).

## ARM CPU Requirements for AL2023

All AL2023 aarch64 (ARM) binaries are built for 64-bit. No 32-bit ARM binaries are available, so a 64-bit ARM CPU is required.

### Note

For Arm-based instances, AL2023 only supports instance types that use Graviton2 or later processors. AL2023 doesn't support A1 instances.

AL2023 requires an ARMv8.2 compliant processor with the Cryptography Extension (ARMv8.2+crypto). All AL2023 packages for aarch64 are built with the `-march=armv8.2-a+crypto` compiler flag. Although we attempt to print graceful error messages when AL2023 code is attempted to be run on older ARM processors, it is possible that the first error message may be an illegal instruction error.

**Note**

Because of the AL2023 aarch64 base CPU requirements, all Raspberry Pi systems prior to the Raspberry Pi 5 do not meet the minimum CPU requirements.

## x86-64 CPU Requirements for AL2023

All AL2023 x86-64 binaries are built for the x86-64v2 revision of the x86-64 architecture by passing `-march=x86-64-v2` to the compiler.

The x86-64v2 revision of the architecture adds the following CPU features on top of the baseline x86-64 architecture:

- CMPXCHG16B
- LAHF-SAHF
- POPCNT
- SSE3
- SSE4\_1
- SSE4\_2
- SSSE3

This roughly maps to x86-64 processors released in 2009 or later. Examples include the Intel Nehalem, AMD Jaguar, Atom Silvermont, along with the VIA Nano and Eden C microarchitectures.

In Amazon EC2, all x86-64 instance types support x86-64v2, including M1, C1, and M2 instance families.

No 32-bit x86 (i686) AL2023 binaries are built. Although AL2023 retains support for running 32-bit userspace binaries, this functionality is deprecated and might be removed in a future major version of Amazon Linux. For more information, see [32bit x86 \(i686\) Packages](#).

## Memory (RAM) requirements for running AL2023

The Amazon EC2 .nano family of instance types (`t2.nano`, `t3.nano`, `t3a.nano`, and `t4g.nano`) have 512 MB RAM which is the minimum requirement for AL2023.

**Note**

Although 512 MB is the minimum requirement, these instance types are memory constrained and functionality and performance may be limited.

AL2023 images have not been tested on systems with less than 512 MB RAM. Running AL2023 based container images in less than 512 MB RAM will be dependent on the containerized workload.

Some workloads, such as `dnf update` between some AL2023 releases can require more than 512 MB RAM. For this reason, the [AL2023.3](#) release introduced enabling `zram` by default for instances with less than 800 MB of RAM. For containerized workloads, this means that some workloads might run fine on AL2023 instances with this amount of memory, but fail when run in a container restricted to this amount of memory usage.

For instance types with less than 800 MB of RAM, AL2023 (as of [AL2023.3](#) or newer) will enable `zram` based swap by default. Examples of Amazon EC2 instance types with less than 800 MB memory include `t4g.nano`, `t3a.nano`, `t3.nano`, `t2.nano`, and `t1.micro`. This means fewer out of memory scenarios for these instance types, because AL2023 will on-demand compress and decompress memory pages. This enables workloads that would otherwise require an instance type with more memory, at the expense of CPU usage needed to do the compression.

# Using AL2023 on AWS

You can set up AL2023 for use with other AWS services. For example, you can choose an AL2023 AMI when you launch an [Amazon Elastic Compute Cloud](#) (Amazon EC2) instance.

For these setup procedures, you use the AWS Identity and Access Management (IAM) service. For complete information about IAM, see the following reference materials:

- [AWS Identity and Access Management \(IAM\)](#)
- [IAM User Guide](#)

## Topics

- [Getting started with AWS](#)
- [AL2023 on Amazon EC2](#)
- [Using AL2023 in containers](#)
- [AL2023 on AWS Elastic Beanstalk](#)
- [Using AL2023 in AWS CloudShell](#)
- [Using AL2023 based Amazon ECS AMIs to host containerized workloads](#)
- [Using Amazon Elastic File System on AL2023](#)
- [Using Amazon EMR built on AL2023](#)
- [Using AL2023 in AWS Lambda](#)

## Getting started with AWS

### Sign up for an AWS account

If you do not have an AWS account, complete the following steps to create one.

#### To sign up for an AWS account

1. Open <https://portal.aws.amazon.com/billing/signup>.
2. Follow the online instructions.

Part of the sign-up procedure involves receiving a phone call and entering a verification code on the phone keypad.

When you sign up for an AWS account, an *AWS account root user* is created. The root user has access to all AWS services and resources in the account. As a security best practice, assign administrative access to a user, and use only the root user to perform [tasks that require root user access](#).

AWS sends you a confirmation email after the sign-up process is complete. At any time, you can view your current account activity and manage your account by going to <https://aws.amazon.com/> and choosing **My Account**.

## Create a user with administrative access

After you sign up for an AWS account, secure your AWS account root user, enable AWS IAM Identity Center, and create an administrative user so that you don't use the root user for everyday tasks.

### Secure your AWS account root user

1. Sign in to the [AWS Management Console](#) as the account owner by choosing **Root user** and entering your AWS account email address. On the next page, enter your password.

For help signing in by using root user, see [Signing in as the root user](#) in the *AWS Sign-In User Guide*.

2. Turn on multi-factor authentication (MFA) for your root user.

For instructions, see [Enable a virtual MFA device for your AWS account root user \(console\)](#) in the *IAM User Guide*.

### Create a user with administrative access

1. Enable IAM Identity Center.

For instructions, see [Enabling AWS IAM Identity Center](#) in the *AWS IAM Identity Center User Guide*.

2. In IAM Identity Center, grant administrative access to a user.

For a tutorial about using the IAM Identity Center directory as your identity source, see [Configure user access with the default IAM Identity Center directory](#) in the *AWS IAM Identity Center User Guide*.

## Sign in as the user with administrative access

- To sign in with your IAM Identity Center user, use the sign-in URL that was sent to your email address when you created the IAM Identity Center user.

For help signing in using an IAM Identity Center user, see [Signing in to the AWS access portal](#) in the *AWS Sign-In User Guide*.

## Assign access to additional users

- In IAM Identity Center, create a permission set that follows the best practice of applying least-privilege permissions.

For instructions, see [Create a permission set](#) in the *AWS IAM Identity Center User Guide*.

- Assign users to a group, and then assign single sign-on access to the group.

For instructions, see [Add groups](#) in the *AWS IAM Identity Center User Guide*.

## Granting programmatic access

Users need programmatic access if they want to interact with AWS outside of the AWS Management Console. The way to grant programmatic access depends on the type of user that's accessing AWS.

To grant users programmatic access, choose one of the following options.

Which user needs programmatic access?	To	By
Workforce identity  (Users managed in IAM Identity Center)	Use temporary credentials to sign programmatic requests to the AWS CLI, AWS SDKs, or AWS APIs.	<p>Following the instructions for the interface that you want to use.</p> <ul style="list-style-type: none"><li>For the AWS CLI, see <a href="#">Configuring the AWS CLI to use AWS IAM Identity Center</a> in the <i>AWS</i></li></ul>

Which user needs programmatic access?	To	By
		<p><i>Command Line Interface User Guide.</i></p> <ul style="list-style-type: none"> <li>For AWS SDKs, tools, and AWS APIs, see <a href="#">IAM Identity Center authentication</a> in the <i>AWS SDKs and Tools Reference Guide</i>.</li> </ul>
IAM	Use temporary credentials to sign programmatic requests to the AWS CLI, AWS SDKs, or AWS APIs.	Following the instructions in <a href="#">Using temporary credentials with AWS resources</a> in the <i>IAM User Guide</i> .
IAM	<p>(Not recommended)</p> <p>Use long-term credentials to sign programmatic requests to the AWS CLI, AWS SDKs, or AWS APIs.</p>	<p>Following the instructions for the interface that you want to use.</p> <ul style="list-style-type: none"> <li>For the AWS CLI, see <a href="#">Authenticating using IAM user credentials</a> in the <i>AWS Command Line Interface User Guide</i>.</li> <li>For AWS SDKs and tools, see <a href="#">Authenticate using long-term credentials</a> in the <i>AWS SDKs and Tools Reference Guide</i>.</li> <li>For AWS APIs, see <a href="#">Managing access keys for IAM users</a> in the <i>IAM User Guide</i>.</li> </ul>

# AL2023 on Amazon EC2

Use one of the following procedures to launch an Amazon EC2 instance with an AL2023 AMI. You can choose either the standard AMI, or the minimal AMI. For more information about the differences between the standard AMI and the minimal AMI, see [Comparing AL2023 standard \(default\) and minimal AMIs](#).

## Topics

- [Launching AL2023 using the Amazon EC2 console](#)
- [Launching AL2023 using the SSM parameter and AWS CLI](#)
- [Launching the latest AL2023 AMI using AWS CloudFormation](#)
- [Launching AL2023 using a specific AMI ID](#)
- [AL2023 AMI deprecation and life cycle](#)
- [Connecting to AL2023 instances](#)
- [Comparing AL2023 standard and minimal AMIs](#)

## Launching AL2023 using the Amazon EC2 console

Use the Amazon EC2 console to launch an AL2023 AMI.

 **Note**

For Arm-based instances, AL2023 only supports instance types that use Graviton2 or later processors. AL2023 doesn't support A1 instances.

Use the following steps to launch an Amazon EC2 instance with an AL2023 AMI from the Amazon EC2 console.

### To launch an EC2 instance with an AL2023 AMI

1. Open the Amazon EC2 console at <https://console.aws.amazon.com/ec2/>.
2. In the navigation pane, choose **AMIs**.
3. From the filter drop-down, choose **Public images**.
4. In the search field, enter **a12023-ami**.


### Note

Make sure that **amazon** appears in the **Owner alias** column.

- Select an image from the list. Under **Source**, you can determine whether the AMI is standard or minimal. An AL2023 AMI name can be interpreted by using this format:

```
'al2023-[ami || ami-minimal]-2023.0.[release build date].[build number]-kernel-[version number]-[arm64 || x86_64]'
```

- The following image shows a partial list of AL2023 AMIs.



A screenshot of the AWS Lambda console. On the left, there's a sidebar with 'Capacity Reservations' and sections for 'Images', 'AMIs' (which is selected), 'AMI Catalog', 'Elastic Block Store', 'Volumes', 'Snapshots', and 'Lifecycle Manager'. The main area has a title 'Amazon Machine Images (AMIs) (4) Info'. Below it is a search bar with 'al2023-ami' and a 'Clear filters' button. There are buttons for 'Public images' and 'Search'. To the right are buttons for 'Recycle Bin', 'EC2 Image Builder', 'Actions', and 'Launch instance from AMI'. A pagination control shows page 1 of 1. The table lists four AMIs:

	Name	AMI ID	AMI name	Source	Owner	Owner alias
<input type="checkbox"/>	-	ami-000a4d9c6067d5d0d	al2023-ami-2023.0.20230222.1...	amazon/al2023-ami-2023.0.20230222.1-kernel-6.1-arm64	137112412989	amazon
<input type="checkbox"/>	-	ami-0a09f5927bd2662f	al2023-ami-2023.0.20230222.1...	amazon/al2023-ami-2023.0.20230222.1-kernel-6.1-x86_64	137112412989	amazon
<input type="checkbox"/>	-	ami-043e11d11b3d437e	al2023-ami-minimal-2023.0.20...	amazon/al2023-ami-minimal-2023.0.20230222.1-kernel-6.1-arm64	137112412989	amazon
<input type="checkbox"/>	-	ami-0d19aa82c9a61ef2c	al2023-ami-minimal-2023.0.20...	amazon/al2023-ami-minimal-2023.0.20230222.1-kernel-6.1-x86_64	137112412989	amazon

For more information about launching Amazon EC2 instances, see [Get started with Amazon EC2 Linux instances](#) in the *Amazon EC2 User Guide*.

## Launching AL2023 using the SSM parameter and AWS CLI

In the AWS CLI, you can use an AMI's SSM parameter value to launch a new instance of AL2023. More specifically, use one of the dynamic SSM parameter values from the following list, and add /aws/service/ami-amazon-linux-latest/ before the SSM parameter value/. You use this to launch the instance in the AWS CLI.

- al2023-ami-kernel-default-arm64 for arm64 architecture
- al2023-ami-minimal-kernel-default-arm64 for arm64 architecture (minimal AMI)
- al2023-ami-kernel-default-x86\_64 for x86\_64 architecture
- al2023-ami-minimal-kernel-default-x86\_64 for x86\_64 architecture (minimal AMI)

**Note**

Each of the *italic* items is an example parameter. Replace them with your own information.

```
$ aws ec2 run-instances \
--image-id \
    resolve:ssm:/aws/service/ami-amazon-linux-latest/al2023-ami-kernel-default-x86_64 \
--instance-type m5.xlarge \
--region us-east-1 \
--key-name aws-key-us-east-1 \
--security-group-ids sg-004a7650
```

The --image-id flag specifies the SSM parameter value.

The --instance-type flag specifies the type and size of the instance. This flag must be compatible with the AMI type that you selected.

The --region flag specifies the AWS Region where you create your instance.

The --key-name flag specifies the AWS Region's key that's used to connect to the instance. If you don't provide a key that exists in the Region where you create the instance, you can't connect to the instance using SSH.

The --security-group-ids flag specifies the security group that determines the access permissions for inbound and outbound network traffic.

**Important**

The AWS CLI requires that you specify an existing security group that allows access to the instance from your remote machine over port TCP:22. Without a specified security group, your new instance are placed in a default security group. In a default security group, your instance can only connect with the other instances within your VPC.

For more information, see [Launching, listing, and terminating Amazon EC2 instances](#) in the *AWS Command Line Interface User Guide*.

# Launching the latest AL2023 AMI using AWS CloudFormation

To launch an AL2023 AMI using AWS CloudFormation, use one of the following templates.

## Note

The x86\_64 and Arm64 AMIs each require different instance types. For more information, see [Amazon EC2 Instance Types](#)

JSON template:

```
{  
  "Parameters": {  
    "LatestAmiId": {  
      "Type": "AWS::SSM::Parameter::Value<AWS::EC2::Image::Id>",  
      "Default": "/aws/service/ami-amazon-linux-latest/al2023-ami-minimal-kernel-  
default-x86_64"  
    }  
  },  
  "Resources": {  
    "MyEC2Instance": {  
      "Type": "AWS::EC2::Instance",  
      "Properties": {  
        "InstanceType": "t2.large",  
        "ImageId": {  
          "Ref": "LatestAmiId"  
        }  
      }  
    }  
  }  
}
```

YAML template:

```
Parameters:  
  LatestAmiId:  
    Type: 'AWS::SSM::Parameter::Value<AWS::EC2::Image::Id>'  
    Default: '/aws/service/ami-amazon-linux-latest/al2023-ami-minimal-kernel-default-  
x86_64'
```

```
Resources:  
  Instance:  
    Type: 'AWS::EC2::Instance'  
    Properties:  
      InstanceType: 't2.large'  
      ImageId: !Ref LatestAmiId
```

Make sure to replace the AMI parameter at the end of the "Default" section, if needed. The following parameter values are available:

- al2023-ami-kernel-6.1-arm64 for arm64 architecture
- al2023-ami-minimal-kernel-6.1-arm64 for arm64 architecture (minimal AMI)
- al2023-ami-kernel-6.1-x86\_64 for x86\_64 architecture
- al2023-ami-minimal-kernel-6.1-x86\_64 for x86\_64 architecture (minimal AMI)

The following are dynamic kernel specifications. The default kernel version automatically changes with each major kernel version update.

- al2023-ami-kernel-default-arm64 for arm64 architecture
- al2023-ami-minimal-kernel-default-arm64 for arm64 architecture (minimal AMI)
- al2023-ami-kernel-default-x86\_64 for x86\_64 architecture
- al2023-ami-minimal-kernel-default-x86\_64 for x86\_64 architecture (minimal AMI)

## Launching AL2023 using a specific AMI ID

You can launch a specific AL2023 AMI using the AMI ID. You can determine which AL2023 AMI ID is needed by looking at the AMI list in the Amazon EC2 console. Or, you can use AWS Systems Manager. If you're using Systems Manager, make sure to select the AMI alias from those that are listed in the previous section. For more information, see [Query for the latest Amazon Linux AMI IDs using AWS Systems Manager Parameter Store](#).

## AL2023 AMI deprecation and life cycle

Each new AL2023 release includes a new AMI. When the AMI is registered, it's marked with a deprecation date. The deprecation date for each AL2023 AMI is 90 days from the time it was released to match the time period that [Kernel Live Patching on AL2023](#) is offered for each individual kernel release.

**Note**

The 90 day deprecation date refers to an individual AMI and doesn't refer to the AL2023 [Release cadence](#) or product support period.

For more information about AMI deprecation, see [Deprecate an AMI](#) in the *Amazon EC2 User Guide*.

Regularly using an updated AMI to launch an instance ensures that the instance starts with the latest security updates, including an updated kernel. If you launch a previous version of an AMI and apply updates, there is a period of time that the instance doesn't have the latest security updates. To ensure you're using the latest AMI, we recommend that you use SSM parameters.

For more information about using SSM parameters to launch an instance, see:

- [Launching AL2023 using the SSM parameter and AWS CLI](#)
- [Launching the latest AL2023 AMI using AWS CloudFormation](#)

## Connecting to AL2023 instances

Use SSH or AWS Systems Manager to connect to your AL2023 instance.

### Connect to your instance using SSH

For instructions on how to use SSH to connect to an instance, see [Connect to your Linux instance using SSH](#) in the *Amazon EC2 User Guide*.

### Connect to your instance using AWS Systems Manager

For instructions on how to use AWS Systems Manager to connect to an AL2023 instance, see [Connect to your Linux instance using Session Manager](#) in the *Amazon EC2 User Guide*.

### Using Amazon EC2 Instance Connect

The AL2023 AMI, excluding the minimal AMI, comes with the EC2 Instance Connect agent installed by default. To use EC2 Instance Connect with an AL2023 instance launched from the minimal AMI, you must install the `ec2-instance-connect` package. For instructions on using EC2 Instance Connect, see [Connect to your Linux instance with EC2 Instance Connect](#) in the *Amazon EC2 User Guide*.

## Comparing AL2023 standard and minimal AMIs

You can launch an Amazon EC2 instance with either a standard (default) or minimal AL2023 AMI. For instructions on how to launch an Amazon EC2 instance with the standard or minimal AMI type, see [AL2023 on Amazon EC2](#).

The standard AL2023 AMI comes with all of the most commonly used applications and tools installed. We recommend the standard AMI if you want to get started quickly and aren't interested in customizing the AMI.

The minimal AL2023 AMI is the basic, streamlined version that contains only the most basic tools and utilities necessary to run the operating system (OS). We recommend the minimal AMI if you want to have the smallest OS footprint possible. The minimal AMI offers slightly reduced disk space utilization and better long-term cost efficiency. The minimal AMI is suitable if you want a smaller OS and don't mind manually installing tools and applications.

The Container image is closer to the AL2023 minimal AMI in package set.

## Comparing packages installed on Amazon Linux 2023 Images

A comparison of the RPMs present on the AL2023 AMI, Minimal AMI, and Container images.

Package	AMI	Minimal AMI	Container
acl	2.3.1		
acpid	2.0.32		
alternatives	1.15	1.15	1.15
amazon-chrony-config	4.3	4.3	
<a href="#">amazon-ec2-net-utils</a>	2.4.1	2.4.1	
amazon-linux-repo-cdn			2023.4.20240513

Package	AMI	Minimal AMI	Container
amazon-linux-repo-s3	2023.4.20240513	2023.4.20240513	
<a href="#"><u>amazon-linux-sb-keys</u></a>	2023.1	2023.1	
amazon-rpm-config	228		
amazon-ssm-agent	3.3.380.0		
at	3.1.23		
attr	2.5.1		
audit	3.0.6	3.0.6	
audit-libs	3.0.6	3.0.6	3.0.6
aws-cfn-bootstrap	2.0		
awscli-2	2.15.30	2.15.30	
basesystem	11	11	11
bash	5.2.15	5.2.15	5.2.15
bash-completion	2.11		
bc	1.07.1		
bind-libs	9.16.48		
bind-license	9.16.48		
bind-utils	9.16.48		

Package	AMI	Minimal AMI	Container
<a href="#">binutils</a>	2.39		
boost-fil esystem	1.75.0		
boost-system	1.75.0		
boost-thread	1.75.0		
bzip2	1.0.8		
bzip2-libs	1.0.8	1.0.8	1.0.8
ca-certificates	2023.2.64	2023.2.64	2023.2.64
c-ares	1.19.0		
checkpolicy	3.4	3.4	
chkconfig	1.15		
chrony	4.3	4.3	
cloud-init	22.2.2	22.2.2	
cloud-init-cfg- ec2	22.2.2	22.2.2	
cloud-utils- growpart	0.31	0.31	
coreutils	8.32	8.32	
coreutils- common	8.32	8.32	
coreutils- single			8.32

Package	AMI	Minimal AMI	Container
cpio	2.13	2.13	
cracklib	2.9.6	2.9.6	
cracklib-dicts	2.9.6	2.9.6	
crontabs	1.11		
crypto-policies	20220428	20220428	20220428
crypto-polices-scripts	20220428		
cryptsetup	2.6.1		
cryptsetup-libs	2.6.1	2.6.1	
<u>curl-minimal</u>	8.5.0	8.5.0	8.5.0
cyrus-sasl-lib	2.1.27	2.1.27	
cyrus-sasl-plain	2.1.27		
dbus	1.12.28	1.12.28	
dbus-broker	32	32	
dbus-common	1.12.28	1.12.28	
dbus-libs	1.12.28	1.12.28	
device-mapper	1.02.185	1.02.185	
device-mapper-libs	1.02.185	1.02.185	
diffutils	3.8	3.8	

Package	AMI	Minimal AMI	Container
dnf	4.14.0	4.14.0	4.14.0
dnf-data	4.14.0	4.14.0	4.14.0
dnf-plugin-release-notification	1.2	1.2	
dnf-plugins-core	4.3.0	4.3.0	
dnf-plugin-support-info	1.2	1.2	
dnf-utils	4.3.0		
dosfstools	4.2		
dracut	055	055	
dracut-config-ec2	3.0	3.0	
dracut-config-generic	055	055	
dwz	0.14		
dyninst	10.2.1		
e2fsprogs	1.46.5	1.46.5	
e2fsprogs-libs	1.46.5	1.46.5	
ec2-hibinit-agent	1.0.8		

Package	AMI	Minimal AMI	Container
ec2-instance-connect	1.1		
ec2-instance-connect-selinux	1.1		
ec2-utils	2.2.0	2.2.0	
ed	1.14.2		
efi-filesystem	5	5	
efi-srpm-macros	5		
efivar	38	38	
efivar-libs	38	38	
elfutils-debuginfod-client	0.188		
elfutils-default-yama-scope	0.188	0.188	0.188
elfutils-libelf	0.188	0.188	0.188
elfutils-libs	0.188	0.188	0.188
ethtool	5.15		
expat	2.5.0	2.5.0	2.5.0
file	5.39	5.39	
file-libs	5.39	5.39	5.39

Package	AMI	Minimal AMI	Container
filesystem	3.14	3.14	3.14
findutils	4.8.0	4.8.0	
fonts-srpm-macros	2.0.5		
fstrm	0.6.1		
fuse-libs	2.9.9	2.9.9	
gawk	5.1.0	5.1.0	5.1.0
gdbm-libs	1.19	1.19	1.19
gdisk	1.0.8	1.0.8	
gettext	0.21	0.21	
gettext-libs	0.21	0.21	
ghc-srpm-macros	1.5.0		
glib2	2.74.7	2.74.7	2.74.7
glibc	2.34	2.34	2.34
glibc-all-langpacks	2.34	2.34	
glibc-common	2.34	2.34	2.34
glibc-gconv-extra	2.34		
glibc-locale-source	2.34	2.34	

Package	AMI	Minimal AMI	Container
glibc-minimal-langpack			2.34
gmp	6.2.1	6.2.1	6.2.1
<a href="#">gnupg2-minimal</a>	2.3.7	2.3.7	2.3.7
gnutls	3.8.0	3.8.0	
go-srpm-macros	3.2.0		
gpgme	1.15.1	1.15.1	1.15.1
gpm-libs	1.20.7		
grep	3.8	3.8	3.8
groff-base	1.22.4	1.22.4	
grub2-common	2.06	2.06	
grub2-efi-aa64-ec2	2.06 (aarch64)	2.06 (aarch64)	
grub2-efi-x64-ec2	2.06 (x86_64)	2.06 (x86_64)	
grub2-pc-modules	2.06	2.06	
grub2-tools	2.06	2.06	
grub2-tools-minimal	2.06	2.06	
grubby	8.40	8.40	
gssproxy	0.8.4		

Package	AMI	Minimal AMI	Container
gzip	1.12	1.12	
hostname	3.23	3.23	
hunspell	1.7.0		
hunspell-en	0.20140811.1		
hunspell-en-GB	0.20140811.1		
hunspell-en-US	0.20140811.1		
hunspell-filesystem	1.7.0		
hwdata	0.353	0.353	
info	6.7		
inih	49	49	
initscripts	10.09	10.09	
iproute	5.10.0	5.10.0	
iputils	20210202	20210202	
irqbalance	1.9.0	1.9.0	
jansson	2.14	2.14	
jitterentropy	3.4.1	3.4.1	
jq	1.7.1	1.7.1	
json-c	0.14	0.14	0.14
kbd	2.4.0	2.4.0	
kbd-misc	2.4.0	2.4.0	

Package	AMI	Minimal AMI	Container
kernel	6.1.90	6.1.90	
kernel-li vepatch-repo- s3	2023.4.20240513	2023.4.20240513	
kernel-srpm- macros	1.0		
kernel-tools	6.1.90		
keyutils	1.6.3		
keyutils-libs	1.6.3	1.6.3	1.6.3
kmod	29	29	
kmod-libs	29	29	
kpatch-runtime	0.9.7		
krb5-libs	1.21	1.21	1.21
less	608	608	
libacl	2.3.1	2.3.1	2.3.1
libaio	0.3.111		
libarchive	3.5.3	3.5.3	3.5.3
libargon2	20171227	20171227	
libassuan	2.5.5	2.5.5	2.5.5
libattr	2.5.1	2.5.1	2.5.1
libbasicobjects	0.1.1		

Package	AMI	Minimal AMI	Container
libblkid	2.37.4	2.37.4	2.37.4
libcap	2.48	2.48	2.48
libcap-ng	0.8.2	0.8.2	0.8.2
libcbor	0.7.0	0.7.0	
libcollection	0.7.0		
libcom_err	1.46.5	1.46.5	1.46.5
libcomps	0.1.20	0.1.20	0.1.20
libconfig	1.7.2		
<a href="#"><u>curl-minimal</u></a>	8.5.0	8.5.0	8.5.0
<a href="#"><u>libdb</u></a>	5.3.28	5.3.28	
libdhash	0.5.0		
libdnf	0.69.0	0.69.0	0.69.0
libeconf	0.4.0	0.4.0	
libedit	3.1	3.1	
libev	4.33		
libevent	2.1.12		
libfdisk	2.37.4	2.37.4	
libffi	3.4.4	3.4.4	3.4.4
libfido2	1.10.0	1.10.0	
libgcc	11.4.1	11.4.1	11.4.1

<b>Package</b>	<b>AMI</b>	<b>Minimal AMI</b>	<b>Container</b>
libgcrypt	1.10.2	1.10.2	1.10.2
libgomp	11.4.1	11.4.1	11.4.1
libgpg-error	1.42	1.42	1.42
libibverbs	48.0		
libidn2	2.3.2	2.3.2	2.3.2
libini_config	1.3.1		
libkapi	1.4.0	1.4.0	
libkapi-hmaccalc	1.4.0	1.4.0	
libldb	2.6.2		
libmaxminddb	1.5.2		
libmetalink	0.1.3		
libmnl	1.0.4	1.0.4	
libmodulemd	2.13.0	2.13.0	2.13.0
libmount	2.37.4	2.37.4	2.37.4
libnfsidmap	2.5.4		
libnghttp2	1.59.0	1.59.0	1.59.0
libnl3	3.5.0		
libpath_utils	0.2.1		
libpcap	1.10.1		
libpipeline	1.5.3	1.5.3	

<b>Package</b>	<b>AMI</b>	<b>Minimal AMI</b>	<b>Container</b>
libpkgconf	1.8.0		
libpsl	0.21.1	0.21.1	0.21.1
libpwquality	1.4.4	1.4.4	
libref_array	0.1.5		
librepo	1.14.5	1.14.5	1.14.5
libreport-filesystem	2.15.2	2.15.2	2.15.2
libseccomp	2.5.3	2.5.3	
libselinux	3.4	3.4	3.4
libselinux-utils	3.4	3.4	
libsemanage	3.4	3.4	
libsepolicy	3.4	3.4	3.4
libsigsegv	2.13	2.13	2.13
libsmartcols	2.37.4	2.37.4	2.37.4
libsolv	0.7.22	0.7.22	0.7.22
libss	1.46.5	1.46.5	
libsss_certmap	2.9.4		
libsss_idmap	2.9.4		
libsss_ns_idmap	2.9.4		

Package	AMI	Minimal AMI	Container
libsss_sudo	2.9.4		
libstdc++	11.4.1	11.4.1	11.4.1
libstoragemgmt	1.9.4		
libtalloc	2.3.4		
libtasn1	4.19.0	4.19.0	4.19.0
libtdb	1.4.7		
libtevent	0.13.0		
libtextstyle	0.21	0.21	
libtirpc	1.3.3		
libunistring	0.9.10	0.9.10	0.9.10
libuser	0.63	0.63	
libutempter	1.2.1	1.2.1	
libuuid	2.37.4	2.37.4	2.37.4
libuv	1.47.0		
libverto	0.3.2	0.3.2	0.3.2
libverto-libev	0.3.2		
libxcrypt	4.4.33	4.4.33	4.4.33
libxml2	2.10.4	2.10.4	2.10.4
libyaml	0.2.5	0.2.5	0.2.5
libzstd	1.5.5	1.5.5	1.5.5

Package	AMI	Minimal AMI	Container
lm_sensors-libs	3.6.0		
lmdb-libs	0.9.29		
logrotate	3.20.1	3.20.1	
lsof	4.94.0		
lua-libs	5.4.4	5.4.4	5.4.4
lua-srpm-macros	1		
lz4-libs	1.9.4	1.9.4	1.9.4
man-db	2.9.3	2.9.3	
man-pages	5.10		
microcode_ctl	2.1 (x86_64)	2.1 (x86_64)	
mpfr	4.1.0	4.1.0	4.1.0
nano	5.8		
ncurses	6.2	6.2	
ncurses-base	6.2	6.2	6.2
ncurses-libs	6.2	6.2	6.2
nettle	3.8	3.8	
net-tools	2.0	2.0	
newt	0.52.21		
nfs-utils	2.5.4		
npth	1.6	1.6	1.6

Package	AMI	Minimal AMI	Container
nspr	4.35.0		
nss	3.90.0		
nss-softokn	3.90.0		
nss-softokn-freebl	3.90.0		
nss-sysinit	3.90.0		
nss-util	3.90.0		
ntsysv	1.15		
numactl-libs	2.0.14	2.0.14	
ocaml-srpm-macros	6		
oniguruma	6.9.7.1	6.9.7.1	
openblas-srpm-macros	2		
openldap	2.4.57	2.4.57	
openssh	8.7p1	8.7p1	
openssh-clients	8.7p1	8.7p1	
openssh-server	8.7p1	8.7p1	
openssl	3.0.8	3.0.8	
openssl-libs	3.0.8	3.0.8	3.0.8
openssl-pkcs11	0.4.12	0.4.12	

Package	AMI	Minimal AMI	Container
os-prober	1.77	1.77	
p11-kit	0.24.1	0.24.1	0.24.1
p11-kit-trust	0.24.1	0.24.1	0.24.1
package-notes-srpm-macros	0.4		
pam	1.5.1	1.5.1	
parted	3.4		
passwd	0.80	0.80	
pciutils	3.7.0	3.7.0	
pciutils-libs	3.7.0	3.7.0	
pcre2	10.40	10.40	10.40
pcre2-syntax	10.40	10.40	10.40
perl-Carp	1.50		
perl-Class-Struct	0.66		
perl-constant	1.33		
perl-DynaLoader	1.47		
perl-Encode	3.15		
perl-Errno	1.30		
perl-Exporter	5.74		
perl-Fcntl	1.13		

Package	AMI	Minimal AMI	Container
perl-File-Basename	2.85		
perl-File-Path	2.18		
perl-File-stat	1.09		
perl-File-Temp	0.231.100		
perl-Getopt-Long	2.52		
perl-Getopt-Std	1.12		
perl-HTTP-Tiny	0.078		
perl-if	0.60.800		
perl-interpreter	5.32.1		
perl-IO	1.43		
perl-IPC-Open3	1.21		
perl-libs	5.32.1		
perl-MIME-Base64	3.16		
perl-mro	1.23		
perl-overload	1.31		
perl-overloading	0.02		
perl-parent	0.238		

Package	AMI	Minimal AMI	Container
perl-PathTools	3.78		
perl-Pod-Escapes	1.07		
perl-podlators	4.14		
perl-Pod-Perldoc	3.28.01		
perl-Pod-Simple	3.42		
perl-Pod-Usage	2.01		
perl-POSIX	1.94		
perl-Scalar-List-Utils	1.56		
perl-SelectSaver	1.02		
perl-Socket	2.032		
perl-srpm-macros	1		
perl-Storable	3.21		
perl-subs	1.03		
perl-Symbol	1.08		
perl-Term-ANSIColor	5.01		
perl-Term-Cap	1.17		

Package	AMI	Minimal AMI	Container
perl-Text-ParseWords	3.30		
perl-Text-Tabs+Wrap	2021.0726		
perl-Time-Local	1.300		
perl-vars	1.05		
pkgconf	1.8.0		
pkgconf-m4	1.8.0		
pkgconf-pkg-config	1.8.0		
policycoreutils	3.4	3.4	
policycoreutils-python-utils	3.4		
popt	1.18	1.18	1.18
procps-ng	3.3.17	3.3.17	
protobuf-c	1.4.1		
psacct	6.6.4		
psmisc	23.4	23.4	
publicsuffix-list-dafsa	20240212	20240212	20240212
python3	3.9.16	3.9.16	3.9.16
python3-attrs	20.3.0	20.3.0	

Package	AMI	Minimal AMI	Container
python3-audit	3.0.6	3.0.6	
python3-awscrt	0.19.19	0.19.19	
python3-babel	2.9.1	2.9.1	
python3-cffi	1.14.5	1.14.5	
python3-chardet	4.0.0	4.0.0	
python3-colorama	0.4.4	0.4.4	
python3-configuration	5.0.6	5.0.6	
python3-cryptography	36.0.1	36.0.1	
python3-daemon	2.3.0		
python3-dateutil	2.8.1	2.8.1	
python3-dbus	1.2.18	1.2.18	
python3-distro	1.5.0	1.5.0	
python3-dnf	4.14.0	4.14.0	4.14.0
python3-dnf-plugins-core	4.3.0	4.3.0	
python3-docutils	0.16	0.16	
python3-gpg	1.15.1	1.15.1	1.15.1
python3-hawkey	0.69.0	0.69.0	0.69.0

<b>Package</b>	<b>AMI</b>	<b>Minimal AMI</b>	<b>Container</b>
python3-idna	2.10	2.10	
python3-jinja2	2.11.3	2.11.3	
python3-jmespath	0.10.0	0.10.0	
python3-joinpatch	1.21	1.21	
python3-jsonpointer	2.0	2.0	
python3-jsonschema	3.2.0	3.2.0	
python3-libcomps	0.1.20	0.1.20	0.1.20
python3-libdnf	0.69.0	0.69.0	0.69.0
python3-libs	3.9.16	3.9.16	3.9.16
python3-libselinux	3.4	3.4	
python3-libsemanage	3.4	3.4	
python3-libstoragegmt	1.9.4		
python3-lockfile	0.12.2		
python3-markupsafe	1.1.1	1.1.1	

<b>Package</b>	<b>AMI</b>	<b>Minimal AMI</b>	<b>Container</b>
python3-netifaces	0.10.6	0.10.6	
python3-oauthlib	3.0.2	3.0.2	
python3-pip-wheel	21.3.1	21.3.1	21.3.1
python3-ply	3.11	3.11	
python3-policycoreutils	3.4	3.4	
python3-prettystable	0.7.2	0.7.2	
python3-prompt-toolkit	3.0.24	3.0.24	
python3-pycparser	2.20	2.20	
python3-pyrsistent	0.17.3	0.17.3	
python3-pyserial	3.4	3.4	
python3-pysocks	1.7.1	1.7.1	
python3-pytz	2022.7.1	2022.7.1	
python3-pyyaml	5.4.1	5.4.1	
python3-requests	2.25.1	2.25.1	

<b>Package</b>	<b>AMI</b>	<b>Minimal AMI</b>	<b>Container</b>
python3-rpm	4.16.1.3	4.16.1.3	4.16.1.3
python3-ruamel-yaml	0.16.6	0.16.6	
python3-ruamel-yaml-lib	0.1.2	0.1.2	
python3-setools	4.4.1	4.4.1	
python3-setuptools	59.6.0	59.6.0	
python3-setuptools-wheel	59.6.0	59.6.0	59.6.0
python3-six	1.15.0	1.15.0	
python3-systemd	235	235	
python3-urllib3	1.25.10	1.25.10	
python3-wcwidth	0.2.5	0.2.5	
python-chevron	0.13.1		
python-srpm-macros	3.9		
quota	4.06		
quota-nls	4.06		
readline	8.1	8.1	8.1
rng-tools	6.14	6.14	
rootfiles	8.1	8.1	

Package	AMI	Minimal AMI	Container
rpcbind	1.2.6		
rpm	4.16.1.3	4.16.1.3	4.16.1.3
rpm-build-libs	4.16.1.3	4.16.1.3	4.16.1.3
rpm-libs	4.16.1.3	4.16.1.3	4.16.1.3
rpm-plugin-selinux	4.16.1.3	4.16.1.3	
rpm-plugin-systemd-inhibit	4.16.1.3	4.16.1.3	
rpm-sign-libs	4.16.1.3	4.16.1.3	4.16.1.3
rsync	3.2.6		
rust-srpm-macros	21		
sbsigntools	0.9.4	0.9.4	
screen	4.8.0		
sed	4.8	4.8	4.8
selinux-policy	37.22	37.22	
selinux-policy-targeted	37.22	37.22	
setup	2.13.7	2.13.7	2.13.7
shadow-utils	4.9	4.9	
slang	2.3.2		
sqlite-libs	3.40.0	3.40.0	3.40.0

Package	AMI	Minimal AMI	Container
sssd-client	2.9.4		
sssd-common	2.9.4		
sssd-kcm	2.9.4		
sssd-nfs-idmap	2.9.4		
strace	6.8		
sudo	1.9.15	1.9.15	
sysctl-defaults	1.0	1.0	
sysstat	12.5.6		
systemd	252.16	252.16	
systemd-libs	252.16	252.16	
systemd-networkd	252.16	252.16	
systemd-pam	252.16	252.16	
systemd-resolved	252.16	252.16	
systemd-udev	252.16	252.16	
system-release	2023.4.20240513	2023.4.20240513	2023.4.20240513
systemtap-runtime	4.8		
tar	1.34	1.34	
tbb	2020.3		

Package	AMI	Minimal AMI	Container
tcpdump	4.99.1		
tcsh	6.24.07		
time	1.9		
traceroute	2.1.3		
tzdata	2024a	2024a	2024a
unzip	6.0		
update-motd	2.2	2.2	
userspace-rcu	0.12.1	0.12.1	
util-linux	2.37.4	2.37.4	
util-linux-core	2.37.4	2.37.4	
vim-common	9.0.2153		
vim-data	9.0.2153	9.0.2153	
vim-enhanced	9.0.2153		
vim-filesystem	9.0.2153		
vim-minimal	9.0.2153	9.0.2153	
wget	1.21.3		
which	2.21	2.21	
words	3.0		
xfsdump	3.1.11		
xfsprogs	5.18.0	5.18.0	

Package	AMI	Minimal AMI	Container
xxd	9.0.2153		
xxhash-libs	0.8.0		
xz	5.2.5	5.2.5	
xz-libs	5.2.5	5.2.5	5.2.5
yum	4.14.0	4.14.0	4.14.0
zip	3.0		
zlib	1.2.11	1.2.11	1.2.11
zram-generator	1.1.2	1.1.2	
zram-generator-defaults	1.1.2	1.1.2	
zstd	1.5.5	1.5.5	

## Using AL2023 in containers

 **Note**

For more information about how to use AL2023 to host containerized workloads on Amazon ECS, see [AL2023 for Amazon ECS container hosts](#).

There are several ways that AL2023 can be used inside containers depending on the use case. The [AL2023 Base Container Image](#) is most similar to an Amazon Linux 2 container image and the AL2023 minimal AMI.

For advanced users, we offer a minimal container image, introduced in the AL2023.2 release, along with documentation that describes how to build [bare-bones containers](#).

AL2023 can also be used to host containerized workloads, either of AL2023 based container images, or containers based on other Linux distributions. You can use [AL2023 for Amazon ECS container hosts](#), or use the provided container runtime packages directly. The docker, containerd, and nerdctl packages are available to be installed and used on AL2023.

## Topics

- [Using the AL2023 base container image](#)
- [AL2023 Minimal container image](#)
- [Building bare-bones AL2023 container images](#)
- [Comparing packages installed on Amazon Linux 2023 Container Images](#)
- [Comparing packages installed on Amazon Linux 2023 Minimal AMI and Container Images](#)

## Using the AL2023 base container image

The AL2023 container image is built from the same software components that are included in the AL2023 AMI. It's available for use in any environment as a base image for Docker workloads. If you're using the Amazon Linux AMI for applications in [Amazon Elastic Compute Cloud](#) (Amazon EC2), you can containerize your applications with the Amazon Linux container image.

Use the Amazon Linux container image in your local development environment and then push your application to AWS using [Amazon Elastic Container Service](#) (Amazon ECS). For more information, see [Using Amazon ECR images with Amazon ECS](#) in the *Amazon Elastic Container Registry User Guide*.

The Amazon Linux container image is available on Amazon ECR Public. You can provide feedback for AL2023 through your designated AWS representative or by filing an issue in the [amazon-linux-2023 repo](#) on GitHub.

### To pull the Amazon Linux container image from Amazon ECR Public

1. Authenticate your Docker client to the Amazon Linux Public registry. Authentication tokens are valid for 12 hours. For more information, see [Private registry authentication](#) in the *Amazon Elastic Container Registry User Guide*.

**Note**

The **get-login-password** command is supported using the latest version of AWS CLI version 2. For more information, see [Installing the AWS Command Line Interface](#) in the *AWS Command Line Interface User Guide*.

```
$ aws ecr-public get-login-password --region us-east-1 | docker login --username AWS --password-stdin public.ecr.aws
```

The output is as follows.

```
Login succeeded
```

2. Pull the Amazon Linux container image by running the **docker pull** command. To view the Amazon Linux container image on the Amazon ECR Public Gallery, see [Amazon ECR Public Gallery - amazonlinux](#).

**Note**

When you pull the AL2023 Docker container image, you can use the tags in one of the following formats:

- To get the latest version of the AL2023 container image, use the :2023 tag.
- To get a specific version of AL2023, you can use the following format:
  - :2023.[*0-7 release quarter*].[*release date*].[*build number*]

The following examples use the tag :2023 and pull the most recent available container image of AL2023.

```
$ docker pull public.ecr.aws/amazonlinux/amazonlinux:2023
```

3. (Optional) Run the container locally.

```
$ docker run -it --security-opt seccomp=unconfined public.ecr.aws/amazonlinux/amazonlinux:2023 /bin/bash
```

## To pull the AL2023 container image from Docker Hub

1. Pull the AL2023 container image using the **docker pull** command.

```
$ docker pull amazonlinux:2023
```

2. (Optional) Run the container locally.

```
$ docker run -it amazonlinux:2023 /bin/bash
```

### Note

The container image of AL2023 uses only the `dnf` package manager to install software packages. This means that there's no `amazon-linux-extras` or equivalent command to use for additional software.

## AL2023 Minimal container image

### Note

The standard AL2023 container images are suitable for most use cases, and adapting to the minimal container image is likely to be more work than adapting to the AL2023 base container image.

The AL2023 minimal container image, introduced in AL2023.2, differs from the base container image because it contains only the bare minimum packages needed to install other packages. The minimal container image is designed to be a minimal set of packages, not a convenient set of packages .

The AL2023 minimal container image is built from software components already available in AL2023. The key difference in the minimal container image is using `microdnf` to provide the `dnf` package manager rather than the fully featured Python based `dnf`. This enables the minimal

container image to be smaller with the trade-off of not having the full feature set of the dnf package manager which is included in the AL2023 AMIs and base container image.

The AL2023 minimal container image forms the base of the provided .al2023 AWS Lambda runtime environment.

For a detailed list of packages included in the minimal container image, see [Comparing packages installed on Amazon Linux 2023 Container Images](#).

## Minimal Container image size

Because the AL2023 minimal container image contains fewer packages than the AL2023 base container image, it is also significantly smaller. The following table compares the container image options of current and past releases of Amazon Linux.

 **Note**

Image Size is as-shown on [Amazon Linux on Amazon ECR Public Gallery](#).

Image	Version	Image Size	Note
Amazon Linux 1 (AL1)	2018.03.0.20230918.0	62.3MB	x86-64 only
Amazon Linux 2	2.0.20230926.0	64.2MB	aarch64 is 1.6MB larger than x86-64
Amazon Linux 2023 base container image	2023.2.20231002.0	52.4MB	
Amazon Linux 2023 minimal container image	2023.2.20231002.0-minimal	35.2MB	

## Using the AL2023 Minimal Container image

The AL2023 minimal container image is available on ECR and the 2023-minimal tag will always point to the latest AL2023 based minimal container image, while the minimal tag may be updated to a newer version of Amazon Linux than AL2023.

You can pull these tags using `docker` with the following example:

```
$ docker pull public.ecr.aws/amazonlinux/amazonlinux:minimal
```

```
$ docker pull public.ecr.aws/amazonlinux/amazonlinux:2023-minimal
```

The following example shows a Dockerfile that takes the minimal container image and installs GCC on top of it :

```
FROM public.ecr.aws/amazonlinux/amazonlinux:2023-minimal
RUN dnf install -y gcc && dnf clean all
```

## Building bare-bones AL2023 container images

The AL2023 container image is built from the same software components that are included in the AL2023 AMI. It includes a software that enables the base container layer to behave similarly to running on an Amazon EC2 instance, such as the package manager `dnf`. This section explains how you can construct a container from scratch that includes only the bare minimum dependencies needed for an application.

### Note

The standard AL2023 container images are suitable for most use cases. Using the standard container image makes it easy to build on top of your image. A bare-bones container image makes it more difficult to build on top of your image.

### To create a container with bare minimum dependencies for an application

1. Determine your runtime dependencies. This will vary based on your application.

2. Construct a Dockerfile / Containerfile that builds FROM scratch. The following example of a Dockerfile can be used to build a container that contains only the bash shell and its dependencies.

```
FROM public.ecr.aws/amazonlinux/amazonlinux:2023 as build
RUN mkdir /sysroot
RUN dnf --releasever=$(rpm -q system-release --qf '%{VERSION}') \
    --installroot /sysroot \
    -y \
    --setopt=install_weak_deps=False \
    install bash

FROM scratch
COPY --from=build /sysroot /
WORKDIR /
ENTRYPOINT ["/bin/bash"]
```

- This Dockerfile works by:
  1. Starting a AL2023 container named build. This container will be used to bootstrap the barebones container, this container is not deployed itself, but generates the container to be deployed.
  2. Creating the /sysroot directory. This directory will be where the build container will install the dependencies needed for the barebones container. In a subsequent step, the /sysroot path will be packaged up to be the root directory of our barebones image.

Using the --installroot option to dnf in this manner is how we create the other AL2023 images. It's a feature of dnf that allows installers and image creation tooling to work.

3. Invoking dnf to install packages into /sysroot.

The rpm -q system-release --qf '%{VERSION}' command queries (-q) the system-release package, setting the query format (--qf) to print out the version of the package being queried (the %{VERSION} variable is the rpm variable for the version of the RPM).

By setting the `--releasever` argument of `dnf` to the version of `system-release` in the build container, this Dockerfile can be used to rebuild the barebones container whenever an updated container base image of Amazon Linux is released.

It is possible to set the `--releasever` to any Amazon Linux 2023 version, such as 2023.5.20240624. Doing this would mean that the build container would run as the latest AL2023 version, but build the barebones container from 2023.5.20240624 regardless of what was the current AL2023 release.

The `--setopt=install_weak_deps=False` configuration option tells `dnf` to only install dependencies that are *required* rather than recommended or suggested.

4. Copying the installed system into the root of a blank (`FROM scratch`) container.
5. Setting the `ENTRYPOINT` to be the desired binary, in this case `/bin/bash`.
3. Create an empty directory and add the content of the example in Step 2 to a file named `Dockerfile`.

```
$ mkdir al2023-barebones-bash-example
$ cd al2023-barebones-bash-example
$ cat > Dockerfile <<EOF
FROM public.ecr.aws/amazonlinux/amazonlinux:2023 as build
RUN mkdir /sysroot
RUN dnf --releasever=$(rpm -q system-release --qf '%{VERSION}') \
    --installroot /sysroot \
    -y \
    --setopt=install_weak_deps=False \
    install bash && dnf --installroot /sysroot clean all

FROM scratch
COPY --from=build /sysroot /
WORKDIR /
ENTRYPOINT ["/bin/bash"]
EOF
```

4. Build the container by running the following command.

```
$ docker build -t al2023-barebones-bash-example
```

5. Run the container using the following command to see how minimal a bash-only container is.

```
$ docker run -it --rm al2023-barebones-bash-example
bash-5.2# rpm
bash: rpm: command not found
bash-5.2# du -sh /usr/
bash: du: command not found
bash-5.2# ls
bash: ls: command not found
bash-5.2# echo /bin/*
/bin/alias /bin/bash /bin/bashbug /bin/bashbug-64 /bin/bg /bin/catchsegv /bin/cd /
bin/command /bin/fc /bin/fg /bin/gencat /bin/getconf /bin/getent /bin/getopts /
bin/hash /bin/iconv /bin/jobs /bin/ld.so /bin/ldd /bin/locale /bin/localedef /
bin/pldd /bin/read /bin/sh /bin/sotruss /bin/sprof /bin/type /bin/tzselect /bin/
ulimit /bin/umask /bin/unalias /bin/wait /bin/zdump
```

For a more practical example, the following procedure builds a container for a C application that displays Hello World!.

1. Create an empty directory and add the C source code and Dockerfile.

```
$ mkdir al2023-barebones-c-hello-world-example
$ cd al2023-barebones-c-hello-world-example
$ cat > hello-world.c <<EOF
#include <stdio.h>
int main(void)
{
    printf("Hello World!\n");
    return 0;
}
EOF

$ cat > Dockerfile <<EOF
FROM public.ecr.aws/amazonlinux/amazonlinux:2023 as build
COPY hello-world.c /
RUN dnf -y install gcc
RUN gcc -o hello-world hello-world.c
RUN mkdir /sysroot
RUN mv hello-world /sysroot/
RUN dnf --releasever=$(rpm -q system-release --qf '%{VERSION}') \
--installroot /sysroot \
-y \
--setopt=install_weak_deps=False \
```

```
install glibc && dnf --installroot /sysroot clean all

FROM scratch
COPY --from=build /sysroot /
WORKDIR /
ENTRYPOINT ["/hello-world"]
EOF
```

- Build the container using the following command.

```
$ docker build -t al2023-barebones-c-hello-world-example .
```

- Run the container using the following command.

```
$ docker run -it --rm al2023-barebones-c-hello-world-example
Hello World!
```

## Comparing packages installed on Amazon Linux 2023 Container Images

A comparison of the RPMs present on the AL2023 base container image compared with the RPMs present on the AL2023 minimal container image.

Package	Container	Minimal Container
alternatives	1.15	1.15
amazon-linux-repo-cdn	2023.4.20240513	2023.4.20240513
audit-libs	3.0.6	3.0.6
basesystem	11	11
bash	5.2.15	5.2.15
bzip2-libs	1.0.8	1.0.8
ca-certificates	2023.2.64	2023.2.64

<b>Package</b>	<b>Container</b>	<b>Minimal Container</b>
coreutils-single	8.32	8.32
crypto-policies	20220428	20220428
<a href="#"><u>curl-minimal</u></a>	8.5.0	8.5.0
dnf	4.14.0	
dnf-data	4.14.0	4.14.0
elfutils-default-y ama-scope	0.188	
elfutils-libelf	0.188	
elfutils-libs	0.188	
expat	2.5.0	
file-libs	5.39	5.39
filesystem	3.14	3.14
gawk	5.1.0	5.1.0
gdbm-libs	1.19	
glib2	2.74.7	2.74.7
glibc	2.34	2.34
glibc-common	2.34	2.34
glibc-minimal-lang pack	2.34	2.34
gmp	6.2.1	6.2.1
<a href="#"><u>gnupg2-minimal</u></a>	2.3.7	2.3.7

Package	Container	Minimal Container
gobject-introspection		1.73.0
gpgme	1.15.1	1.15.1
grep	3.8	3.8
json-c	0.14	0.14
keyutils-libs	1.6.3	1.6.3
krb5-libs	1.21	1.21
libacl	2.3.1	2.3.1
libarchive	3.5.3	3.5.3
libassuan	2.5.5	2.5.5
libattr	2.5.1	2.5.1
libblkid	2.37.4	2.37.4
libcap	2.48	2.48
libcap-ng	0.8.2	0.8.2
libcom_err	1.46.5	1.46.5
libcomps	0.1.20	
<a href="#"><u>libcurl-minimal</u></a>	8.5.0	8.5.0
libdnf	0.69.0	0.69.0
libffi	3.4.4	3.4.4
libgcc	11.4.1	11.4.1
libgcrypt	1.10.2	1.10.2

<b>Package</b>	<b>Container</b>	<b>Minimal Container</b>
libgomp	11.4.1	
libgpg-error	1.42	1.42
libidn2	2.3.2	2.3.2
libmodulemd	2.13.0	2.13.0
libmount	2.37.4	2.37.4
libnghttp2	1.59.0	1.59.0
libpeas		1.32.0
libpsl	0.21.1	0.21.1
librepo	1.14.5	1.14.5
libreport-filesystem	2.15.2	2.15.2
libselinux	3.4	3.4
libsepol	3.4	3.4
libsigsegv	2.13	2.13
libsmartcols	2.37.4	2.37.4
libsolv	0.7.22	0.7.22
libstdc++	11.4.1	11.4.1
libtasn1	4.19.0	4.19.0
libunistring	0.9.10	0.9.10
libuuid	2.37.4	2.37.4
libverto	0.3.2	0.3.2

<b>Package</b>	<b>Container</b>	<b>Minimal Container</b>
libxcrypt	4.4.33	
libxml2	2.10.4	2.10.4
libyaml	0.2.5	0.2.5
libzstd	1.5.5	1.5.5
lua-libs	5.4.4	5.4.4
lz4-libs	1.9.4	1.9.4
microdnf		3.8.1
microdnf-dnf		3.8.1
mpfr	4.1.0	4.1.0
ncurses-base	6.2	6.2
ncurses-libs	6.2	6.2
npth	1.6	1.6
openssl-libs	3.0.8	3.0.8
p11-kit	0.24.1	0.24.1
p11-kit-trust	0.24.1	0.24.1
pcre2	10.40	10.40
pcre2-syntax	10.40	10.40
popt	1.18	1.18
publicsuffix-list-dafsa	20240212	20240212
python3	3.9.16	

<b>Package</b>	<b>Container</b>	<b>Minimal Container</b>
python3-dnf	4.14.0	
python3-gpg	1.15.1	
python3-hawkey	0.69.0	
python3-libcomps	0.1.20	
python3-libdnf	0.69.0	
python3-libs	3.9.16	
python3-pip-wheel	21.3.1	
python3-rpm	4.16.1.3	
python3-setuptools-wheel	59.6.0	
readline	8.1	8.1
rpm	4.16.1.3	4.16.1.3
rpm-build-libs	4.16.1.3	
rpm-libs	4.16.1.3	4.16.1.3
rpm-sign-libs	4.16.1.3	
sed	4.8	4.8
setup	2.13.7	2.13.7
sqlite-libs	3.40.0	3.40.0
system-release	2023.4.20240513	2023.4.20240513
tzdata	2024a	
xz-libs	5.2.5	5.2.5

Package	Container	Minimal Container
yum	4.14.0	
zlib	1.2.11	1.2.11

## Comparing packages installed on Amazon Linux 2023 Minimal AMI and Container Images

A comparison of the RPMs present on the AL2023 Minimal AMI to the RPMs present on the AL2023 base and minimal container images.

Package	Minimal AMI	Container	Minimal Container
alternatives	1.15	1.15	1.15
amazon-chrony-config	4.3		
<a href="#"><u>amazon-ec2-net-utils</u></a>	2.4.1		
amazon-linux-repo-cdn		2023.4.20240513	2023.4.20240513
amazon-linux-repo-s3	2023.4.20240513		
<a href="#"><u>amazon-linux-sb-keys</u></a>	2023.1		
audit	3.0.6		
audit-libs	3.0.6	3.0.6	3.0.6
awscli-2	2.15.30		
basesystem	11	11	11

Package	Minimal AMI	Container	Minimal Container
bash	5.2.15	5.2.15	5.2.15
bzip2-libs	1.0.8	1.0.8	1.0.8
ca-certificates	2023.2.64	2023.2.64	2023.2.64
checkpolicy	3.4		
chrony	4.3		
cloud-init	22.2.2		
cloud-init-cfg-ec2	22.2.2		
cloud-utils-growpart	0.31		
coreutils	8.32		
coreutils-common	8.32		
coreutils-single		8.32	8.32
cpio	2.13		
cracklib	2.9.6		
cracklib-dicts	2.9.6		
crypto-policies	20220428	20220428	20220428
cryptsetup-libs	2.6.1		
<a href="#"><u>curl-minimal</u></a>	8.5.0	8.5.0	8.5.0
cyrus-sasl-lib	2.1.27		

<b>Package</b>	<b>Minimal AMI</b>	<b>Container</b>	<b>Minimal Container</b>
dbus	1.12.28		
dbus-broker	32		
dbus-common	1.12.28		
dbus-libs	1.12.28		
device-mapper	1.02.185		
device-mapper-libs	1.02.185		
diffutils	3.8		
dnf	4.14.0	4.14.0	
dnf-data	4.14.0	4.14.0	4.14.0
dnf-plugin-release-notification	1.2		
dnf-plugins-core	4.3.0		
dnf-plugin-support-info	1.2		
dracut	055		
dracut-config-ec2	3.0		
dracut-config-generic	055		
e2fsprogs	1.46.5		

<b>Package</b>	<b>Minimal AMI</b>	<b>Container</b>	<b>Minimal Container</b>
e2fsprogs-libs	1.46.5		
ec2-utils	2.2.0		
efi-filesystem	5		
efivar	38		
efivar-libs	38		
elfutils-default-yama-scope	0.188	0.188	
elfutils-libelf	0.188	0.188	
elfutils-libs	0.188	0.188	
expat	2.5.0	2.5.0	
file	5.39		
file-libs	5.39	5.39	5.39
filesystem	3.14	3.14	3.14
findutils	4.8.0		
fuse-libs	2.9.9		
gawk	5.1.0	5.1.0	5.1.0
gdbm-libs	1.19	1.19	
gdisk	1.0.8		
gettext	0.21		
gettext-libs	0.21		

<b>Package</b>	<b>Minimal AMI</b>	<b>Container</b>	<b>Minimal Container</b>
glib2	2.74.7	2.74.7	2.74.7
glibc	2.34	2.34	2.34
glibc-all-langpacks	2.34		
glibc-common	2.34	2.34	2.34
glibc-locale-source	2.34		
glibc-minimal-langpack		2.34	2.34
gmp	6.2.1	6.2.1	6.2.1
<a href="#"><u>gnupg2-minimal</u></a>	2.3.7	2.3.7	2.3.7
gnutls	3.8.0		
gobject-introspection			1.73.0
gpgme	1.15.1	1.15.1	1.15.1
grep	3.8	3.8	3.8
groff-base	1.22.4		
grub2-common	2.06		
grub2-efi-aa64-ec2	2.06 (aarch64)		
grub2-efi-x64-ec2	2.06 (x86_64)		

<b>Package</b>	<b>Minimal AMI</b>	<b>Container</b>	<b>Minimal Container</b>
grub2-pc-modules	2.06		
grub2-tools	2.06		
grub2-tools-minimal	2.06		
grubby	8.40		
gzip	1.12		
hostname	3.23		
hwdata	0.353		
inih	49		
initscripts	10.09		
iproute	5.10.0		
iutils	20210202		
irqbalance	1.9.0		
jansson	2.14		
jitterentropy	3.4.1		
jq	1.7.1		
json-c	0.14	0.14	0.14
kbd	2.4.0		
kbd-misc	2.4.0		
kernel	6.1.90		

Package	Minimal AMI	Container	Minimal Container
kernel- vepatch-repo- s3	2023.4.20240513		
keyutils-libs	1.6.3	1.6.3	1.6.3
kmod	29		
kmod-libs	29		
krb5-libs	1.21	1.21	1.21
less	608		
libacl	2.3.1	2.3.1	2.3.1
libarchive	3.5.3	3.5.3	3.5.3
libargon2	20171227		
libassuan	2.5.5	2.5.5	2.5.5
libattr	2.5.1	2.5.1	2.5.1
libblkid	2.37.4	2.37.4	2.37.4
libcap	2.48	2.48	2.48
libcap-ng	0.8.2	0.8.2	0.8.2
libcbor	0.7.0		
libcom_err	1.46.5	1.46.5	1.46.5
libcomps	0.1.20	0.1.20	
<a href="#"><u>libcurl-minimal</u></a>	8.5.0	8.5.0	8.5.0
<a href="#"><u>libdb</u></a>	5.3.28		

<b>Package</b>	<b>Minimal AMI</b>	<b>Container</b>	<b>Minimal Container</b>
libdnf	0.69.0	0.69.0	0.69.0
libeconf	0.4.0		
libedit	3.1		
libfdisk	2.37.4		
libffi	3.4.4	3.4.4	3.4.4
libfido2	1.10.0		
libgcc	11.4.1	11.4.1	11.4.1
libgcrypt	1.10.2	1.10.2	1.10.2
libgomp	11.4.1	11.4.1	
libgpg-error	1.42	1.42	1.42
libidn2	2.3.2	2.3.2	2.3.2
libkapi	1.4.0		
libkapi-hmaccalc	1.4.0		
libmnl	1.0.4		
libmodulemd	2.13.0	2.13.0	2.13.0
libmount	2.37.4	2.37.4	2.37.4
libnghttp2	1.59.0	1.59.0	1.59.0
libpeas			1.32.0
libpipeline	1.5.3		
libpsl	0.21.1	0.21.1	0.21.1

<b>Package</b>	<b>Minimal AMI</b>	<b>Container</b>	<b>Minimal Container</b>
libpwquality	1.4.4		
librepo	1.14.5	1.14.5	1.14.5
libreport-filesystem	2.15.2	2.15.2	2.15.2
libseccomp	2.5.3		
libselinux	3.4	3.4	3.4
libselinux-utils	3.4		
libsemanage	3.4		
libsepolicy	3.4	3.4	3.4
libsigsegv	2.13	2.13	2.13
libsmartcols	2.37.4	2.37.4	2.37.4
libsolv	0.7.22	0.7.22	0.7.22
libss	1.46.5		
libstdc++	11.4.1	11.4.1	11.4.1
libtasn1	4.19.0	4.19.0	4.19.0
libtextstyle	0.21		
libunistring	0.9.10	0.9.10	0.9.10
libuser	0.63		
libutempter	1.2.1		
libuuid	2.37.4	2.37.4	2.37.4

<b>Package</b>	<b>Minimal AMI</b>	<b>Container</b>	<b>Minimal Container</b>
libverto	0.3.2	0.3.2	0.3.2
libxcrypt	4.4.33	4.4.33	
libxml2	2.10.4	2.10.4	2.10.4
libyaml	0.2.5	0.2.5	0.2.5
libzstd	1.5.5	1.5.5	1.5.5
logrotate	3.20.1		
lua-libs	5.4.4	5.4.4	5.4.4
lz4-libs	1.9.4	1.9.4	1.9.4
man-db	2.9.3		
microcode_ctl	2.1 (x86_64)		
microdnf			3.8.1
microdnf-dnf			3.8.1
mpfr	4.1.0	4.1.0	4.1.0
ncurses	6.2		
ncurses-base	6.2	6.2	6.2
ncurses-libs	6.2	6.2	6.2
nettle	3.8		
net-tools	2.0		
npth	1.6	1.6	1.6
numactl-libs	2.0.14		

Package	Minimal AMI	Container	Minimal Container
oniguruma	6.9.7.1		
openldap	2.4.57		
openssh	8.7p1		
openssh-clients	8.7p1		
openssh-server	8.7p1		
openssl	3.0.8		
openssl-libs	3.0.8	3.0.8	3.0.8
openssl-pkcs11	0.4.12		
os-prober	1.77		
p11-kit	0.24.1	0.24.1	0.24.1
p11-kit-trust	0.24.1	0.24.1	0.24.1
pam	1.5.1		
passwd	0.80		
pciutils	3.7.0		
pciutils-libs	3.7.0		
pcre2	10.40	10.40	10.40
pcre2-syntax	10.40	10.40	10.40
policycoreutils	3.4		
popt	1.18	1.18	1.18
procps-ng	3.3.17		

<b>Package</b>	<b>Minimal AMI</b>	<b>Container</b>	<b>Minimal Container</b>
psmisc	23.4		
publicsuffix-list-dafsa	20240212	20240212	20240212
python3	3.9.16	3.9.16	
python3-attrs	20.3.0		
python3-audit	3.0.6		
python3-awscrt	0.19.19		
python3-babel	2.9.1		
python3-cffi	1.14.5		
python3-chardet	4.0.0		
python3-colorama	0.4.4		
python3-configurationobj	5.0.6		
python3-cryptography	36.0.1		
python3-dateutil	2.8.1		
python3-dbus	1.2.18		
python3-distro	1.5.0		
python3-dnf	4.14.0	4.14.0	
python3-dnf-plugins-core	4.3.0		

<b>Package</b>	<b>Minimal AMI</b>	<b>Container</b>	<b>Minimal Container</b>
python3-d ocutils	0.16		
python3-gpg	1.15.1	1.15.1	
python3-hawkey	0.69.0	0.69.0	
python3-idna	2.10		
python3-jinja2	2.11.3		
python3-j mespath	0.10.0		
python3-j sonpatch	1.21		
python3-j sonpointer	2.0		
python3-j sonschema	3.2.0		
python3-l ibcomps	0.1.20	0.1.20	
python3-libdnf	0.69.0	0.69.0	
python3-libs	3.9.16	3.9.16	
python3-l ibselinux	3.4		
python3-l ibsemanage	3.4		
python3-m arkupsafe	1.1.1		

<b>Package</b>	<b>Minimal AMI</b>	<b>Container</b>	<b>Minimal Container</b>
python3-n etifaces	0.10.6		
python3-o authlib	3.0.2		
python3-pip- wheel	21.3.1	21.3.1	
python3-ply	3.11		
python3-p olicycoreutils	3.4		
python3-p rettytable	0.7.2		
python3-prompt- toolkit	3.0.24		
python3-p ycparser	2.20		
python3-p ersistent	0.17.3		
python3-p yserial	3.4		
python3-pysocks	1.7.1		
python3-pytz	2022.7.1		
python3-pyyaml	5.4.1		
python3-r equests	2.25.1		

<b>Package</b>	<b>Minimal AMI</b>	<b>Container</b>	<b>Minimal Container</b>
python3-rpm	4.16.1.3	4.16.1.3	
python3-ruamel-yaml	0.16.6		
python3-ruamel-yaml-lib	0.1.2		
python3-setools	4.4.1		
python3-setuptools	59.6.0		
python3-setuptools-wheel	59.6.0	59.6.0	
python3-six	1.15.0		
python3-systemd	235		
python3-urllib3	1.25.10		
python3-wcwidth	0.2.5		
readline	8.1	8.1	8.1
rng-tools	6.14		
rootfiles	8.1		
rpm	4.16.1.3	4.16.1.3	4.16.1.3
rpm-build-libs	4.16.1.3	4.16.1.3	
rpm-libs	4.16.1.3	4.16.1.3	4.16.1.3
rpm-plugin-selinux	4.16.1.3		

<b>Package</b>	<b>Minimal AMI</b>	<b>Container</b>	<b>Minimal Container</b>
<code>rpm-plugin-systemd-inhibit</code>	4.16.1.3		
<code>rpm-sign-libs</code>	4.16.1.3	4.16.1.3	
<code>sbsigntools</code>	0.9.4		
<code>sed</code>	4.8	4.8	4.8
<code>selinux-policy</code>	37.22		
<code>selinux-policy-targeted</code>	37.22		
<code>setup</code>	2.13.7	2.13.7	2.13.7
<code>shadow-utils</code>	4.9		
<code>sqlite-libs</code>	3.40.0	3.40.0	3.40.0
<code>sudo</code>	1.9.15		
<code>sysctl-defaults</code>	1.0		
<code>systemd</code>	252.16		
<code>systemd-libs</code>	252.16		
<code>systemd-networkd</code>	252.16		
<code>systemd-pam</code>	252.16		
<code>systemd-resolved</code>	252.16		
<code>systemd-udev</code>	252.16		
<code>system-release</code>	2023.4.20240513	2023.4.20240513	2023.4.20240513

<b>Package</b>	<b>Minimal AMI</b>	<b>Container</b>	<b>Minimal Container</b>
tar	1.34		
tzdata	2024a	2024a	
update-motd	2.2		
userspace-rcu	0.12.1		
util-linux	2.37.4		
util-linux-core	2.37.4		
vim-data	9.0.2153		
vim-minimal	9.0.2153		
which	2.21		
xfsprogs	5.18.0		
xz	5.2.5		
xz-libs	5.2.5	5.2.5	5.2.5
yum	4.14.0	4.14.0	
zlib	1.2.11	1.2.11	1.2.11
zram-generator	1.1.2		
zram-generator-defaults	1.1.2		
zstd	1.5.5		

## AL2023 on AWS Elastic Beanstalk

AWS Elastic Beanstalk is a service for deploying and scaling web applications and services. Upload your code and Elastic Beanstalk automatically handles the deployment — from capacity provisioning, load balancing, and auto scaling to application health monitoring. For more information, see [AWS Elastic Beanstalk](#).

To use Elastic Beanstalk, you create an application, upload an application version in the form of an application source bundle (for example, a Java .war file) to Elastic Beanstalk, and then provide some information about the application. Elastic Beanstalk automatically launches an environment and creates and configures the AWS resources needed to run your code. For more information, see the [AWS Elastic Beanstalk Developer Guide](#).

Elastic Beanstalk Linux platforms use Amazon EC2 instances, and these instances run Amazon Linux. As of August 4, 2023, Elastic Beanstalk offers the following platform branches based on Amazon Linux 2023: Docker, Tomcat, Java SE, Node.js, PHP, and Python. Elastic Beanstalk is working on releasing support for AL2023 to more Elastic Beanstalk platforms.

The full list of Elastic Beanstalk platform support and current platforms built on top of AL2023 can be found in the [Elastic Beanstalk Linux platforms](#) section of the [Elastic Beanstalk Developer Guide](#).

You can find the Release Notes for new Elastic Beanstalk platforms and versions of existing platforms in the [Elastic Beanstalk Release Notes](#).

## Using AL2023 in AWS CloudShell

AWS CloudShell is a browser-based, pre-authenticated shell that you can launch directly from the AWS Management Console. You can navigate to CloudShell from the AWS Management Console a few different ways. For more information, see [How to get started with AWS CloudShell?](#)

AWS CloudShell, which is currently based on Amazon Linux 2, will migrate to AL2023. The migration to AL2023 will begin to roll out in all AWS Regions starting on December 4, 2023. For more information about CloudShell migrating to AL2023, see [AWS CloudShell migrating from Amazon Linux 2 to Amazon Linux 2023](#).

# Using AL2023 based Amazon ECS AMIs to host containerized workloads

## Note

For more information on how to use AL2023 inside a container, see [AL2023 in containers](#).

Amazon Elastic Container Service (Amazon ECS) is a fully managed container orchestration service that helps you easily deploy, manage, and scale containerized applications. As a fully managed service, Amazon ECS comes with AWS configuration and operational best practices built-in. It's integrated with both AWS and third-party tools, such as Amazon Elastic Container Registry (Amazon ECR) and Docker. This integration makes it easier for teams to focus on building the applications, not the environment. You can run and scale your container workloads across AWS Regions in the cloud, without the complexity of managing a control plane.

You can host containerized workloads on AL2023 using the AL2023 based Amazon ECS-optimized AMI. For more information, see the [Amazon ECS-optimized AMI](#)

## Changes in AL2023 for Amazon ECS compared to AL2

As with AL2, AL2023 provides the base packages required to run as an Amazon ECS Linux instance. In AL2 the `containerd`, `docker`, and `ecs-init` packages were available through `amazon-linux-extras`, whereas AL2023 includes these packages in the core repositories.

With the deterministic upgrades through versioned repositories feature, every AL2023 AMI by default is locked to a specific repository version. This is also true for the AL2023 Amazon ECS optimized AMI. All updates to your environment can be carefully managed and tested prior to deployment, as well as providing an easy way to revert to the content of a prior AMI in the event of an issue. For more information on this AL2023 feature, see [Using Deterministic upgrades through versioned repository on AL2023](#).

AL2023 switches to cgroup v2 over the cgroup v1 interface supported in AL2. For more information, see [Unified Control Group hierarchy \(cgroup v2\)](#).

## Note

AL2023 versions prior to [2023.2.20230920](#) (the first AL2023.2 release) contained a bug in `systemd` for Out-of-Memory (OOM) handling inside a cgroup. All processes in the cgroup

were always killed instead of the OOM-Killer choosing one process at a time, which is the intended behavior.

This was a regression when compared to AL2 behavior, and is fixed as of the 2023.2.20230920 release of AL2023.

The code to build the Amazon ECS-optimized AMI is available on the [amazon-ecs-ami GitHub project](#). The [release notes](#) describe which AL2023 version maps to which Amazon ECS AMI version.

## Customizing the AL2023 based Amazon ECS-optimized AMI

### Important

We recommend that you use the Amazon ECS optimized AL2023 AMI. For more information, see [Amazon ECS-optimized AMI](#) in the *Amazon Elastic Container Service Developer Guide*.

You can use the same build scripts that Amazon ECS uses to create custom AMIs. For more information, see [Amazon ECS-optimized Linux AMI build script](#).

## Using Amazon Elastic File System on AL2023

Amazon Elastic File System (Amazon EFS) provides serverless, fully elastic file storage so that you can share file data without provisioning or managing storage capacity and performance. Amazon EFS is built to scale on demand to petabytes without disrupting applications, growing and shrinking automatically as you add and remove files. Because Amazon EFS has a simple web services interface, you can create and configure file systems quickly and easily. The service manages all the file storage infrastructure for you, meaning that you can avoid the complexity of deploying, patching, and maintaining complex file system configurations.

Amazon EFS supports the Network File System version 4 (NFSv4.1 and NFSv4.0) protocol, so the applications and tools that you use today work seamlessly with Amazon EFS. Multiple compute instances, including Amazon EC2, Amazon ECS, and AWS Lambda, can access an Amazon EFS file system at the same time. Therefore, an EFS file system can provide a common data source for workloads and applications that are running on more than one compute instance or server.

## Installing amazon-efs-utils on AL2023

The `amazon-efs-utils` package is available in the AL2023 repositories to be installed and used to access Amazon EFS file systems.

### Install the `amazon-efs-utils` package on AL2023

- Install `amazon-efs-utils` using the following command.

```
$ dnf -y install amazon-efs-utils
```

## Mounting an Amazon EFS file system on AL2023

After `amazon-efs-utils` is installed, you can mount an Amazon EFS file system on your AL2023 instance.

### Mount an Amazon EFS file system on AL2023

- To mount using the file system id, use the following command.

```
sudo mount -t efs file-system-id efs-mount-point/
```

You can also mount the file system so that data in transit is encrypted using TLS, or by using the DNS name or mount target IP instead of the file system id. For more information, see [Mounting on Amazon Linux instances using the EFS mount helper](#).

## Using Amazon EMR built on AL2023

Amazon EMR is a web service that makes it easy to process vast amounts of data efficiently using Apache Hadoop and services offered by AWS.

### AL2023 based Amazon EMR releases

Amazon EMR release 7.0.0 was the first release built on AL2023. With this release, AL2023 is the base operating system for Amazon EMR, bringing all the advantages of AL2023 to Amazon EMR. For more information, see the [Amazon EMR 7.0.0 release notes](#).

## AL2023 based Amazon EMR on EKS

Amazon EMR on EKS 6.13 was the first release introducing AL2023 as an option. With this release, you can launch Spark with AL2023 as the operating system, together with Java 17 runtime. For more information, see the [Amazon EMR on EKS 6.13 release notes](#), and all [Amazon EMR on EKS release notes](#).

## Using AL2023 in AWS Lambda

With AWS Lambda, you can run code without provisioning or managing servers. You pay only for the compute time that you consume—there's no charge when your code isn't running. You can run code for virtually any type of application or backend service—all with zero administration. Just upload your code and Lambda takes care of everything required to run and scale your code with high availability.

### AL2023 provided.al2023 managed runtime and container image

The provided.al2023 base runtime is based on the [AL2023 minimal container image](#), and provides an AL2023 based Lambda managed runtime and [container base image](#). Because the provided.al2023 runtime is based on the AL2023 minimal container image, it is substantially smaller at less than 40 MB than the provided.al2 runtime at around 109 MB.

For more information, see [Lambda runtimes](#) and [Working with Lambda container images](#).

## AL2023 based Lambda runtimes

Future releases of managed language runtimes, such as Node.js 20, Python 3.12, Java 21, and .NET 8, are based on AL2023 and will use provided.al2023 as the base image as described in the [announcement of AL2023 based runtimes](#).

### AL2023 based Lambda functions

- [AL2023 Lambda functions written in Go](#)
- [AL2023 Lambda functions written in Rust](#)

For more information, see [Lambda runtimes](#) in the *AWS Lambda Developer Guide*.

# Tutorials

The following tutorials show you how to perform common tasks using Amazon EC2 instances running Amazon Linux 2023 (AL2023). For video tutorials, see [AWS Instructional videos and labs](#).

For AL2 instructions, see [Tutorials for Amazon EC2 instances running Linux](#) in the *Amazon EC2 User Guide*.

## Tutorials

- [Tutorial: Install a LAMP server on AL2023](#)
- [Tutorial: Configure SSL/TLS on AL2023](#)
- [Tutorial: Host a WordPress blog on AL2023](#)

## Tutorial: Install a LAMP server on AL2023

The following procedures help you install an Apache web server with PHP and [MariaDB](#) (a community-developed fork of MySQL) support on your AL2023 instance (sometimes called a LAMP web server or LAMP stack). You can use this server to host a static website or deploy a dynamic PHP application that reads and writes information to a database.

### Important

These procedures are intended for use with AL2023. If you are trying to set up a LAMP web server on a different distribution, such as Ubuntu or Red Hat Enterprise Linux, this tutorial will not work. For Ubuntu, see the following Ubuntu community documentation: [ApacheMySQLPHP](#). For other distributions, see their specific documentation.

## Tasks

- [Step 1: Prepare the LAMP server](#)
- [Step 2: Test your LAMP server](#)
- [Step 3: Secure the database server](#)
- [Step 4: \(Optional\) Install phpMyAdmin](#)
- [Troubleshoot](#)
- [Related topics](#)

# Step 1: Prepare the LAMP server

## Prerequisites

- This tutorial assumes that you have already launched a new instance using AL2023, with a public DNS name that is reachable from the internet. For more information, see [AL2023 on Amazon EC2](#). You must also have configured your security group to allow SSH (port 22), HTTP (port 80), and HTTPS (port 443) connections. For more information about these prerequisites, see [Authorize inbound traffic for your Linux instances](#) in the *Amazon EC2 User Guide*.
- The following procedure installs the latest PHP version available on AL2023, currently 8.1. If you plan to use PHP applications other than those described in this tutorial, you should check their compatibility with 8.1.

## To prepare the LAMP server

1. Connect to your instance. For more information, see [Connecting to AL2023 instances](#).
2. To ensure that all of your software packages are up to date, perform a quick software update on your instance. This process might take a few minutes, but it is important to make sure that you have the latest security updates and bug fixes.

The `-y` option installs the updates without asking for confirmation. If you would like to examine the updates before installing, you can omit this option.

```
[ec2-user ~]$ sudo dnf update -y
```

3. Install the latest versions of Apache web server and PHP packages for AL2023.

```
[ec2-user ~]$ sudo dnf install -y httpd wget php-fpm php-mysqli php-json php php-devel
```

4. Install the MariaDB software packages. Use the `dnf install` command to install multiple software packages and all related dependencies at the same time.

```
[ec2-user ~]$ sudo dnf install mariadb105-server
```

You can view the current versions of these packages using the following command:

```
[ec2-user ~]$ sudo dnf info package_name
```

## Example:

```
[root@ip-172-31-25-170 ec2-user]# dnf info mariadb105
Last metadata expiration check: 0:00:16 ago on Tue Feb 14 21:35:13 2023.
Installed Packages
Name        : mariadb105
Epoch       : 3
Version     : 10.5.16
Release    : 1.amzn2023.0.6
Architecture: x86_64
Size        : 18 M
Source      : mariadb105-10.5.16-1.amzn2023.0.6.src.rpm
Repository  : @System
From repo   : amazonlinux
Summary     : A very fast and robust SQL database server
URL         : http://mariadb.org
License     : GPLv2 and LGPLv2
Description  : MariaDB is a community developed fork from MySQL - a multi-user,
               multi-threaded
               : SQL database server. It is a client/server implementation consisting
               of
               : a server daemon (mariadb) and many different client programs and
               libraries.
               : The base package contains the standard MariaDB/MySQL client programs
               and
               : utilities.
```

## 5. Start the Apache web server.

```
[ec2-user ~]$ sudo systemctl start httpd
```

## 6. Use the **systemctl** command to configure the Apache web server to start at each system boot.

```
[ec2-user ~]$ sudo systemctl enable httpd
```

You can verify that **httpd** is on by running the following command:

```
[ec2-user ~]$ sudo systemctl is-enabled httpd
```

## 7. Add a security rule to allow inbound HTTP (port 80) connections to your instance if you have not already done so. By default, a **launch-wizard-N** security group was created for your

instance during launch. If you did not add additional security group rules, this group contains only a single rule to allow SSH connections.

- a. Open the Amazon EC2 console at <https://console.aws.amazon.com/ec2/>.
- b. In the left navigator, choose **Instances**, and select your instance.
- c. On the **Security** tab, view the inbound rules. You should see the following rule:

Port range	Protocol	Source
22	tcp	0.0.0.0/0

 **Warning**

Using `0.0.0.0/0` allows all IPv4 addresses to access your instance using SSH. This is acceptable for a short time in a test environment, but it's unsafe for production environments. In production, you authorize only a specific IP address or range of addresses to access your instance.

- d. If there is no inbound rule to allow HTTP (port 80) connections, you must add a rule now. Choose the link for the security group. Using the procedures in see [Authorize inbound traffic for your Linux instances](#), add a new inbound security rule with the following values:
  - **Type:** HTTP
  - **Protocol:** TCP
  - **Port Range:** 80
  - **Source:** Custom
8. Test your web server. In a web browser, type the public DNS address (or the public IP address) of your instance. If there is no content in `/var/www/html`, you should see the Apache test page, which will display the message "**It works!**".

You can get the public DNS for your instance using the Amazon EC2 console (check the **Public IPv4 DNS** column; if this column is hidden, choose **Preferences** (the gear-shaped icon) and toggle on **Public IPv4 DNS**).

Verify that the security group for the instance contains a rule to allow HTTP traffic on port 80. For more information, see [Add rules to security group](#).

### **⚠️ Important**

If you are not using Amazon Linux, you might also need to configure the firewall on your instance to allow these connections. For more information about how to configure the firewall, see the documentation for your specific distribution.

Apache **httpd** serves files that are kept in a directory called the Apache document root. The Amazon Linux Apache document root is `/var/www/html`, which by default is owned by root.

To allow the `ec2-user` account to manipulate files in this directory, you must modify the ownership and permissions of the directory. There are many ways to accomplish this task. In this tutorial, you add `ec2-user` to the `apache` group to give the `apache` group ownership of the `/var/www` directory and assign write permissions to the group.

### **To set file permissions**

1. Add your user (in this case, `ec2-user`) to the `apache` group.

```
[ec2-user ~]$ sudo usermod -a -G apache ec2-user
```

2. Log out and then log back in again to pick up the new group, and then verify your membership.
  - a. Log out (use the `exit` command or close the terminal window):

```
[ec2-user ~]$ exit
```
  - b. To verify your membership in the `apache` group, reconnect to your instance, and then run the following command:

```
[ec2-user ~]$ groups
ec2-user adm wheel apache systemd-journal
```
3. Change the group ownership of `/var/www` and its contents to the `apache` group.

```
[ec2-user ~]$ sudo chown -R ec2-user:apache /var/www
```

4. To add group write permissions and to set the group ID on future subdirectories, change the directory permissions of /var/www and its subdirectories.

```
[ec2-user ~]$ sudo chmod 2775 /var/www && find /var/www -type d -exec sudo chmod 2775 {} \;
```

5. To add group write permissions, recursively change the file permissions of /var/www and its subdirectories:

```
[ec2-user ~]$ find /var/www -type f -exec sudo chmod 0664 {} \;
```

Now, ec2-user (and any future members of the apache group) can add, delete, and edit files in the Apache document root, enabling you to add content, such as a static website or a PHP application.

### To secure your web server (Optional)

A web server running the HTTP protocol provides no transport security for the data that it sends or receives. When you connect to an HTTP server using a web browser, the URLs that you visit, the content of webpages that you receive, and the contents (including passwords) of any HTML forms that you submit are all visible to eavesdroppers anywhere along the network pathway. The best practice for securing your web server is to install support for HTTPS (HTTP Secure), which protects your data with SSL/TLS encryption.

For information about enabling HTTPS on your server, see [Tutorial: Configure SSL/TLS on AL2023](#).

## Step 2: Test your LAMP server

If your server is installed and running, and your file permissions are set correctly, your ec2-user account should be able to create a PHP file in the /var/www/html directory that is available from the internet.

### To test your LAMP server

1. Create a PHP file in the Apache document root.

```
[ec2-user ~]$ echo "<?php phpinfo(); ?>" > /var/www/html/phpinfo.php
```

If you get a "Permission denied" error when trying to run this command, try logging out and logging back in again to pick up the proper group permissions that you configured in [To set file permissions](#).

2. In a web browser, type the URL of the file that you just created. This URL is the public DNS address of your instance followed by a forward slash and the file name. For example:

`http://my.public.dns.amazonaws.com/phpinfo.php`

You should see the PHP information page:

<b>PHP Version 8.1.7</b>	
<b>System</b>	Linux ip-172-31-16-77.ec2.internal 5.15.57-28.127.amzn2022.aarch64 #1 SMP Thu Aug 4 17:06:57 UTC 2022 aarch64
<b>Build Date</b>	Jun 7 2022 18:21:38
<b>Build System</b>	Linux
<b>Build Provider</b>	Amazon Linux
<b>Compiler</b>	gcc (GCC) 11.3.1 20220421 (Red Hat 11.3.1-2)
<b>Architecture</b>	aarch64
<b>Server API</b>	FPM/FastCGI
<b>Virtual Directory Support</b>	disabled
<b>Configuration File (php.ini) Path</b>	/etc
<b>Loaded Configuration File</b>	/etc/php.ini
<b>Scan this dir for additional .ini files</b>	/etc/php.d
<b>Additional .ini files parsed</b>	/etc/php.d/10-opcache.ini, /etc/php.d/20-bz2.ini, /etc/php.d/20-calendar.ini, /etc/php.d/20-ctype.ini, /etc/php.d/20-curl.ini, /etc/php.d/20-dom.ini, /etc/php.d/20-exif.ini, /etc/php.d/20-fileinfo.ini, /etc/php.d/20-ftp.ini, /etc/php.d/20-gd.ini, /etc/php.d/20-gettext.ini, /etc/php.d/20-iconv.ini, /etc/php.d/20-mbstring.ini, /etc/php.d/20-mysqlind.ini, /etc/php.d/20-pdo.ini, /etc/php.d/20-phar.ini, /etc/php.d/20-simplexml.ini, /etc/php.d/20-sockets.ini, /etc/php.d/20-sqlite3.ini, /etc/php.d/20-tokenizer.ini, /etc/php.d/20-xml.ini, /etc/php.d/20-xmlwriter.ini, /etc/php.d/20-xsl.ini, /etc/php.d/30-mysqli.ini, /etc/php.d/30-pdo_mysql.ini, /etc/php.d/30-pdo_sqlite.ini, /etc/php.d/30-xmlreader.ini
<b>PHP API</b>	20210902
<b>PHP Extension</b>	20210902
<b>Zend Extension</b>	420210902
<b>Zend Extension Build</b>	API420210902,NTS
<b>PHP Extension Build</b>	API20210902,NTS
<b>Debug Build</b>	no
<b>Thread Safety</b>	disabled
<b>Zend Signal Handling</b>	enabled
<b>Zend Memory Manager</b>	enabled
<b>Zend Multibyte Support</b>	provided by mbstring
<b>IPv6 Support</b>	enabled
<b>DTrace Support</b>	available, disabled
<b>Registered PHP Streams</b>	https, ftps, compress.zlib, php, file, glob, data, http, ftp, compress.bzip2, phar
<b>Registered Stream Socket Transports</b>	tcp, udp, unix, udg, ssl, tls, tlsv1.0, tlsv1.1, tlsv1.2, tlsv1.3
<b>Registered Stream Filters</b>	zlib.* , string.rot13, string.toupper, string.tolower, convert.* , consumed, dechunk, bzip2.* , convert.iconv.*
This program makes use of the Zend Scripting Language Engine: Zend Engine v4.1.7, Copyright (c) Zend Technologies with Zend OPcache v8.1.7, Copyright (c), by Zend Technologies	
<b>zendengine</b>	

If you do not see this page, verify that the `/var/www/html/phpinfo.php` file was created properly in the previous step. You can also verify that all of the required packages were installed with the following command.

```
[ec2-user ~]$ sudo dnf list installed httpd mariadb-server php-mysqlnd
```

If any of the required packages are not listed in your output, install them with the `sudo yum install package` command.

3. Delete the `phpinfo.php` file. Although this can be useful information, it should not be broadcast to the internet for security reasons.

```
[ec2-user ~]$ rm /var/www/html/phpinfo.php
```

You should now have a fully functional LAMP web server. If you add content to the Apache document root at `/var/www/html`, you should be able to view that content at the public DNS address for your instance.

## Step 3: Secure the database server

The default installation of the MariaDB server has several features that are great for testing and development, but they should be disabled or removed for production servers. The `mysql_secure_installation` command walks you through the process of setting a root password and removing the insecure features from your installation. Even if you are not planning on using the MariaDB server, we recommend performing this procedure.

### To secure the MariaDB server

1. Start the MariaDB server.

```
[ec2-user ~]$ sudo systemctl start mariadb
```

2. Run `mysql_secure_installation`.

```
[ec2-user ~]$ sudo mysql_secure_installation
```

- a. When prompted, type a password for the root account.

- i. Type the current root password. By default, the root account does not have a password set. Press Enter.
- ii. Type **Y** to set a password, and type a secure password twice. For more information about creating a secure password, see <https://identitysafe.norton.com/password-generator/>. Make sure to store this password in a safe place.

Setting a root password for MariaDB is only the most basic measure for securing your database. When you build or install a database-driven application, you typically create a database service user for that application and avoid using the root account for anything but database administration.

- b. Type **Y** to remove the anonymous user accounts.
  - c. Type **Y** to disable the remote root login.
  - d. Type **Y** to remove the test database.
  - e. Type **Y** to reload the privilege tables and save your changes.
3. (Optional) If you do not plan to use the MariaDB server right away, stop it. You can restart it when you need it again.

```
[ec2-user ~]$ sudo systemctl stop mariadb
```

4. (Optional) If you want the MariaDB server to start at every boot, type the following command.

```
[ec2-user ~]$ sudo systemctl enable mariadb
```

## Step 4: (Optional) Install phpMyAdmin

[phpMyAdmin](#) is a web-based database management tool that you can use to view and edit the MySQL databases on your EC2 instance. Follow the steps below to install and configure phpMyAdmin on your Amazon Linux instance.

### Important

We do not recommend using phpMyAdmin to access a LAMP server unless you have enabled SSL/TLS in Apache; otherwise, your database administrator password and other data are transmitted insecurely across the internet. For security recommendations from

the developers, see [Securing your phpMyAdmin installation](#). For general information about securing a web server on an EC2 instance, see [Tutorial: Configure SSL/TLS on AL2023](#).

## To install phpMyAdmin

1. Install the required dependencies.

```
[ec2-user ~]$ sudo dnf install php-mbstring php-xml -y
```

2. Restart Apache.

```
[ec2-user ~]$ sudo systemctl restart httpd
```

3. Restart php-fpm.

```
[ec2-user ~]$ sudo systemctl restart php-fpm
```

4. Navigate to the Apache document root at /var/www/html.

```
[ec2-user ~]$ cd /var/www/html
```

5. Select a source package for the latest phpMyAdmin release from <https://www.phpmyadmin.net/downloads>. To download the file directly to your instance, copy the link and paste it into a `wget` command, as in this example:

```
[ec2-user html]$ wget https://www.phpmyadmin.net/downloads/phpMyAdmin-latest-all-languages.tar.gz
```

6. Create a phpMyAdmin folder and extract the package into it with the following command.

```
[ec2-user html]$ mkdir phpMyAdmin && tar -xvzf phpMyAdmin-latest-all-languages.tar.gz -C phpMyAdmin --strip-components 1
```

7. Delete the **phpMyAdmin-latest-all-languages.tar.gz** tarball.

```
[ec2-user html]$ rm phpMyAdmin-latest-all-languages.tar.gz
```


8. (Optional) If the MySQL server is not running, start it now.

```
[ec2-user ~]$ sudo systemctl start mariadb
```

9. In a web browser, type the URL of your phpMyAdmin installation. This URL is the public DNS address (or the public IP address) of your instance followed by a forward slash and the name of your installation directory. For example:

```
http://my.public.dns.amazonaws.com/phpMyAdmin
```

You should see the phpMyAdmin login page:



10. Log in to your phpMyAdmin installation with the `root` user name and the MySQL root password you created earlier.

Your installation must still be configured before you put it into service. We suggest that you begin by manually creating the configuration file, as follows:

- a. To start with a minimal configuration file, use your favorite text editor to create a new file, and then copy the contents of config.sample.inc.php into it.
- b. Save the file as config.inc.php in the phpMyAdmin directory that contains index.php.
- c. Refer to post-file creation instructions in the [Using the Setup script](#) section of the phpMyAdmin installation instructions for any additional setup.

For information about using phpMyAdmin, see the [phpMyAdmin User Guide](#).

## Troubleshoot

This section offers suggestions for resolving common problems you might encounter while setting up a new LAMP server.

### I can't connect to my server using a web browser

Perform the following checks to see if your Apache web server is running and accessible.

- **Is the web server running?**

You can verify that **httpd** is on by running the following command:

```
[ec2-user ~]$ sudo systemctl is-enabled httpd
```

If the **httpd** process is not running, repeat the steps described in [To prepare the LAMP server](#).

- **Is the firewall correctly configured?**

Verify that the security group for the instance contains a rule to allow HTTP traffic on port 80. For more information, see [Add rules to security group](#).

### I can't connect to my server using HTTPS

Perform the following checks to see if your Apache web server is configured to support HTTPS.

- **Is the web server correctly configured?**

After you install Apache, the server is configured for HTTP traffic. To support HTTPS, enable TLS on the server and install an SSL certificate. For information, see [Tutorial: Configure SSL/TLS on AL2023](#).

- **Is the firewall correctly configured?**

Verify that the security group for the instance contains a rule to allow HTTPS traffic on port 443. For more information, see [Authorize inbound traffic for your Linux instances](#).

## Related topics

For more information about transferring files to your instance or installing a WordPress blog on your web server, see the following documentation:

- [Transfer files to your Linux instance using WinSCP](#) in the *Amazon EC2 User Guide*.
- [Transfer files to Linux instances using an SCP client](#) in the *Amazon EC2 User Guide*.
- [Tutorial: Host a WordPress blog on AL2023](#)

For more information about the commands and software used in this tutorial, see the following webpages:

- Apache web server: <http://httpd.apache.org/>
- MariaDB database server: <https://mariadb.org/>
- PHP programming language: <http://php.net/>

For more information about registering a domain name for your web server, or transferring an existing domain name to this host, see [Creating and Migrating Domains and Subdomains to Amazon Route 53](#) in the *Amazon Route 53 Developer Guide*.

## Tutorial: Configure SSL/TLS on AL2023

Secure Sockets Layer/Transport Layer Security (SSL/TLS) creates an encrypted channel between a web server and web client that protects data in transit from being eavesdropped on. This tutorial explains how to add support manually for SSL/TLS on an EC2 instance with AL2023 and Apache web server. This tutorial assumes that you are not using a load balancer. If you are using Elastic

Load Balancing, you can choose to configure SSL offload on the load balancer, using a certificate from [AWS Certificate Manager](#) instead.

For historical reasons, web encryption is often referred to simply as SSL. While web browsers still support SSL, its successor protocol TLS is less vulnerable to attack. AL2023 disables server-side support for all versions of SSL by default. [Security standards bodies](#) consider TLS 1.0 to be unsafe. TLS 1.0 and TLS 1.1 were formally [deprecated](#) in March 2021. This tutorial contains guidance based exclusively on enabling TLS 1.2. TLS 1.3 was finalized in 2018 and is available in AL2 as long as the underlying TLS library (OpenSSL in this tutorial) is supported and enabled. [Clients must support TLS 1.2 or later by June 28, 2023](#). For more information about the updated encryption standards, see [RFC 7568](#) and [RFC 8446](#).

This tutorial refers to modern web encryption simply as TLS.

### **Important**

These procedures are intended for use with AL2023. If you are trying to set up an EC2 instance running a different distribution, or an instance running an old version of Amazon Linux, some procedures in this tutorial might not work. For Ubuntu, see the following Ubuntu community documentation: [Open SSL on Ubuntu](#). For Red Hat Enterprise Linux, see the following: [Setting up the Apache HTTP Web Server](#). For other distributions, see their specific documentation.

### **Note**

Alternatively, you can use AWS Certificate Manager (ACM) for AWS Nitro enclaves, which is an enclave application that allows you to use public and private SSL/TLS certificates with your web applications and servers running on Amazon EC2 instances with AWS Nitro Enclaves. Nitro Enclaves is an Amazon EC2 capability that enables creation of isolated compute environments to protect and securely process highly sensitive data, such as SSL/TLS certificates and private keys.

ACM for Nitro Enclaves works with **nginx** running on your Amazon EC2 Linux instance to create private keys, to distribute certificates and private keys, and to manage certificate renewals.

To use ACM for Nitro Enclaves, you must use an enclave-enabled Linux instance.

For more information, see [What is AWS Nitro Enclaves?](#) and [AWS Certificate Manager for Nitro Enclaves](#) in the *AWS Nitro Enclaves User Guide*.

## Contents

- [Prerequisites](#)
- [Step 1: Enable TLS on the server](#)
- [Step 2: Obtain a CA-signed certificate](#)
- [Step 3: Test and harden the security configuration](#)
- [Troubleshoot](#)

## Prerequisites

Before you begin this tutorial, complete the following steps:

- Launch an EBS-backed AL2023 instance. For more information, see [AL2023 on Amazon EC2](#).
- Configure your security groups to allow your instance to accept connections on the following TCP ports:
  - SSH (port 22)
  - HTTP (port 80)
  - HTTPS (port 443)

For more information, see [Authorize inbound traffic for your Linux instances](#) in the *Amazon EC2 User Guide*.

- Install the Apache web server. For step-by-step instructions, see [Tutorial: Install a LAMP server on AL2023](#). Only the httpd package and its dependencies are needed, so you can ignore the instructions involving PHP and MariaDB.
- To identify and authenticate websites, the TLS public key infrastructure (PKI) relies on the Domain Name System (DNS). To use your EC2 instance to host a public website, you need to register a domain name for your web server or transfer an existing domain name to your Amazon EC2 host. Numerous third-party domain registration and DNS hosting services are available for this, or you can use [Amazon Route 53](#).

## Step 1: Enable TLS on the server

This procedure takes you through the process of setting up TLS on AL2023 with a self-signed digital certificate.

### Note

A self-signed certificate is acceptable for testing but not production. If you expose your self-signed certificate to the internet, visitors to your site are greeted by security warnings.

### To enable TLS on a server

1. Connect to your instance and confirm that Apache is running. For more information, see [Connecting to AL2023 instances](#).

```
[ec2-user ~]$ sudo systemctl is-enabled httpd
```

If the returned value is not "enabled," start Apache and set it to start each time the system boots.

```
[ec2-user ~]$ sudo systemctl start httpd && sudo systemctl enable httpd
```

2. To ensure that all of your software packages are up to date, perform a quick software update on your instance. This process may take a few minutes, but it is important to make sure that you have the latest security updates and bug fixes.

### Note

The `-y` option installs the updates without asking for confirmation. If you would like to examine the updates before installing, you can omit this option.

```
[ec2-user ~]$ sudo dnf install openssl mod_ssl
```

3. After you enter the following command, you will be taken to a prompt where you can enter information about your site.

```
[ec2-user ~]$ sudo openssl req -x509 -nodes -days 365 -newkey rsa:2048 -keyout /etc/pki/tls/private/apache-selfsigned.key -out /etc/pki/tls/certs/apache-selfsigned.crt
```

This generates a new file `apache-selfsigned.crt` in the `/etc/pki/tls/certs/` directory. The specified file name matches the default that is assigned in the **SSLCertificateFile** directive in `/etc/httpd/conf.d/ssl.conf`.

Your instance now has the following files that you use to configure your secure server and create a certificate for testing:

- `/etc/httpd/conf.d/ssl.conf`

The configuration file for mod\_ssl. It contains *directives* telling Apache where to find encryption keys and certificates, the TLS protocol versions to allow, and the encryption ciphers to accept. This will be your local certificate file:

- `/etc/pki/tls/certs/apache-selfsigned.crt`

This file contains both a self-signed certificate and the certificate's private key. Apache requires the certificate and key to be in PEM format, which consists of Base64-encoded ASCII characters framed by "BEGIN" and "END" lines, as in the following abbreviated example.

```
-----BEGIN PRIVATE KEY-----
MIEvgIBADANBgkqhkiG9w0BAQEFAASCBKgwggSkAgEAAoIBAQD2KKx/8Zk94m1q
3gQMZF9ZN66Ls19+3tHAgQ5Fpo9KJDhzLj00CI8u1PTcGmAah5kEitCEc0wzmNeo
BC10wYR6G0rGaKtK9Dn7CuIjvubtUysVyQoMVPQ971deakHWeRMiEJFXg6kZZ0vr
GwnKoMh3D1K44D9dX7IDua2P1Yx5+eroA+1Lqf32ZSaA00bBIMIYTHigwbHMZoT
...
56tE7THvH7v0Ef4/iUOsIrEzaMaJ0mqkmY1A70qQGQKBgBF3H1qNRNHuyMcPODFs
27hDzPDinrquSEvoZIggkDMlh2irTiipJ/GhkvtPoQ1v0fK/VXw8vSgeaBuhwJvS
LXU9HvYq0U604FgD3nAyB9hI0BE13r1HjUvbjT7moH+RhnNz6eqqdscCS09VtRAo
4QQvAq0a8UheYeoXLdwChalP
-----END PRIVATE KEY-----

-----BEGIN CERTIFICATE-----
MIEazCCA10gAwIBAgICWxQwDQYJKoZIhvcNAQELBQAwgbExCzAJBgNVBAYTAi0t
MRIwEAYDVQQIDA1Tb211U3RhGUxETAPBgNVBAcMCFNvbWVDaXR5MRkwFwYDVQQK
DBBTb211T3JnYW5pemF0aW9uMR8wHQYDVQQLDzTb211T3JnYW5pemF0aW9uYWxV
bm10MRkwFwYDVQQDDBpcC0xNzItMzEtMjAtMjM2MSQwIgYJKoZIhvcNAQkBFhVy
```

```
...
z5rUE/XzxRLBZ0oWZpNWTXJkQ3uFYH6s/sBwtHpKKZMz0vDedREjNKAvk4ws6F0
CuIjvubtUysVyQoMVPQ971deakHWeRMiEJFXg6kZZ0vrGvwnKoMh3D1K44D9d1U3
WanXWehT6FiSZvB4sTEXXJN2jdw8g+sHGnZ8zC0sclknYhHrCVD2vnBlZJKSzvak
3ZazhBxtQSukFMOnWPP2a0DMMFGYUH0d0BQE8sBJxg==
-----END CERTIFICATE-----
```

The file names and extensions are a convenience and have no effect on function. For example, you can call a certificate `cert.crt`, `cert.pem`, or any other file name, so long as the related directive in the `ssl.conf` file uses the same name.

 **Note**

When you replace the default TLS files with your own customized files, be sure that they are in PEM format.

4. Restart Apache.

```
[ec2-user ~]$ sudo systemctl restart httpd
```

 **Note**

Make sure that TCP port 443 is accessible on your EC2 instance, as previously described.

5. Your Apache web server should now support HTTPS (secure HTTP) over port 443. Test it by entering the IP address or fully qualified domain name of your EC2 instance into a browser URL bar with the prefix **https://**.

Because you are connecting to a site with a self-signed, untrusted host certificate, your browser may display a series of security warnings. Override the warnings and proceed to the site.

If the default Apache test page opens, it means that you have successfully configured TLS on your server. All data passing between the browser and server is now encrypted.

**Note**

To prevent site visitors from encountering warning screens, you must obtain a trusted, CA-signed certificate that not only encrypts, but also publicly authenticates you as the owner of the site.

## Step 2: Obtain a CA-signed certificate

You can use the following process to obtain a CA-signed certificate:

- Generate a certificate signing request (CSR) from a private key
- Submit the CSR to a certificate authority (CA)
- Obtain a signed host certificate
- Configure Apache to use the certificate

A self-signed TLS X.509 host certificate is cryptologically identical to a CA-signed certificate. The difference is social, not mathematical. A CA promises, at a minimum, to validate a domain's ownership before issuing a certificate to an applicant. Each web browser contains a list of CAs trusted by the browser vendor to do this. An X.509 certificate consists primarily of a public key that corresponds to your private server key, and a signature by the CA that is cryptographically tied to the public key. When a browser connects to a web server over HTTPS, the server presents a certificate for the browser to check against its list of trusted CAs. If the signer is on the list, or accessible through a *chain of trust* consisting of other trusted signers, the browser negotiates a fast encrypted data channel with the server and loads the page.

Certificates generally cost money because of the labor involved in validating the requests, so it pays to shop around. A few CAs offer basic-level certificates free of charge. The most notable of these CAs is the [Let's Encrypt](#) project, which also supports the automation of the certificate creation and renewal process. For more information about using a Let's Encrypt certificate, see [Get Certbot](#).

If you plan to offer commercial-grade services, [AWS Certificate Manager](#) is a good option.

Underlying the host certificate is the key. As of 2019, [government](#) and [industry](#) groups recommend using a minimum key (modulus) size of 2048 bits for RSA keys intended to protect documents,

through 2030. The default modulus size generated by OpenSSL in AL2023 is 2048 bits, which is suitable for use in a CA-signed certificate. In the following procedure, an optional step provided for those who want a customized key, for example, one with a larger modulus or using a different encryption algorithm.

### **⚠ Important**

These instructions for acquiring a CA-signed host certificate do not work unless you own a registered and hosted DNS domain.

## To obtain a CA-signed certificate

1. Connect to your instance and navigate to `/etc/pki/tls/private/`. This is the directory where you store the server's private key for TLS. If you prefer to use an existing host key to generate the CSR, skip to Step 3. For more information about connecting to your instance, see [Connecting to AL2023 instances](#)
2. (Optional) Generate a new private key. Here are some examples of key configurations. Any of the resulting keys works with your web server, but they vary in the degree and type of security that they implement.
  - **Example 1:** Create a default RSA host key. The resulting file, `custom.key`, is a 2048-bit RSA private key.

```
[ec2-user ~]$ sudo openssl genrsa -out custom.key
```

- **Example 2:** Create a stronger RSA key with a bigger modulus. The resulting file, `custom.key`, is a 4096-bit RSA private key.

```
[ec2-user ~]$ sudo openssl genrsa -out custom.key 4096
```

- **Example 3:** Create a 4096-bit encrypted RSA key with password protection. The resulting file, `custom.key`, is a 4096-bit RSA private key encrypted with the AES-128 cipher.

### **⚠ Important**

Encrypting the key provides greater security, but because an encrypted key requires a password, services depending on it cannot be auto-started. Each time you use this

key, you must supply the password (in the preceding example, "abcde12345") over an SSH connection.

```
[ec2-user ~]$ sudo openssl genrsa -aes128 -passout pass:abcde12345 -out custom.key 4096
```

- **Example 4:** Create a key using a non-RSA cipher. RSA cryptography can be relatively slow because of the size of its public keys, which are based on the product of two large prime numbers. However, it is possible to create keys for TLS that use non-RSA ciphers. Keys based on the mathematics of elliptic curves are smaller and computationally faster when delivering an equivalent level of security.

```
[ec2-user ~]$ sudo openssl ecparam -name prime256v1 -out custom.key -genkey
```

The result is a 256-bit elliptic curve private key using prime256v1, a "named curve" that OpenSSL supports. Its cryptographic strength is slightly greater than a 2048-bit RSA key, [according to NIST](#).

#### Note

Not all CAs provide the same level of support for elliptic-curve-based keys as for RSA keys.

Make sure that the new private key has highly restrictive ownership and permissions (owner=root, group=root, read/write for owner only). The commands would be as shown in the following example.

```
[ec2-user ~]$ sudo chown root:root custom.key  
[ec2-user ~]$ sudo chmod 600 custom.key  
[ec2-user ~]$ ls -al custom.key
```

The preceding commands yield the following result.

```
-rw----- root root custom.key
```

After you have created and configured a satisfactory key, you can create a CSR.

3. Create a CSR using your preferred key. The following example uses **custom.key**.

```
[ec2-user ~]$ sudo openssl req -new -key custom.key -out csr.pem
```

OpenSSL opens a dialog and prompts you for the information shown in the following table. All of the fields except **Common Name** are optional for a basic, domain-validated host certificate.

Name	Description	Example
Country Name	The two-letter ISO abbreviation for your country.	US (=United States)
State or Province Name	The name of the state or province where your organization is located. This name cannot be abbreviated.	Washington
Locality Name	The location of your organization, such as a city.	Seattle
Organization Name	The full legal name of your organization. Do not abbreviate your organization name.	Example Corporation
Organizational Unit Name	Additional organizational information, if any.	Example Dept
Common Name	This value must exactly match the web address that you expect users to enter into a browser. Usually, this means a domain name with a prefixed hostname or alias in the form <b>www.example.com</b> . In testing with a self-signed certificate and no DNS resolution, the common name may consist of the hostname alone. CAs also offer more expensive certificates that accept wild-card names such as <b>*.example.com</b> .	www.example.com

Name	Description	Example
Email Address	The server administrator's email address.	someone@example.com

Finally, OpenSSL prompts you for an optional challenge password. This password applies only to the CSR and to transactions between you and your CA, so follow the CA's recommendations about this and the other optional field, optional company name. The CSR challenge password has no effect on server operation.

The resulting file **csr.pem** contains your public key, your digital signature of your public key, and the metadata that you entered.

4. Submit the CSR to a CA. This usually consists of opening your CSR file in a text editor and copying the contents into a web form. At this time, you may be asked to supply one or more subject alternate names (SANs) to be placed on the certificate. If **www.example.com** is the common name, then **example.com** would be a good SAN, and vice versa. A visitor to your site entering either of these names would see an error-free connection. If your CA web form allows it, include the common name in the list of SANs. Some CAs include it automatically.

After your request has been approved, you receive a new host certificate signed by the CA. You might also be instructed to download an *intermediate certificate* file that contains additional certificates needed to complete the CA's chain of trust.

### Note

Your CA might send you files in multiple formats intended for various purposes. For this tutorial, you should only use a certificate file in PEM format, which is usually (but not always) marked with a **.pem** or **.crt** file extension. If you are uncertain which file to use, open the files with a text editor and find the one containing one or more blocks beginning with the following line.

```
- - - - -BEGIN CERTIFICATE - - - - -
```

The file should also end with the following line.

```
- - - - -END CERTIFICATE - - - - -
```

You can also test the file at the command line as shown in the following.

```
[ec2-user certs]$ openssl x509 -in certificate.crt -text
```

Verify that these lines appear in the file. Do not use files ending with .p7b, .p7c, or similar file extensions.

5. Place the new CA-signed certificate and any intermediate certificates in the /etc/pki/tls/certs directory.

 **Note**

There are several ways to upload your new certificate to your EC2 instance, but the most straightforward and informative way is to open a text editor (for example, vi, nano, or notepad) on both your local computer and your instance, and then copy and paste the file contents between them. You need root [sudo] permissions when performing these operations on the EC2 instance. This way, you can see immediately if there are any permission or path problems. Be careful, however, not to add any additional lines while copying the contents, or to change them in any way.

From inside the /etc/pki/tls/certs directory, check that the file ownership, group, and permission settings match the highly restrictive AL2023 defaults (owner=root, group=root, read/write for owner only). The following example shows the commands to use.

```
[ec2-user certs]$ sudo chown root:root custom.crt  
[ec2-user certs]$ sudo chmod 600 custom.crt  
[ec2-user certs]$ ls -al custom.crt
```

These commands should yield the following result.

```
-rw----- root root custom.crt
```

The permissions for the intermediate certificate file are less stringent (owner=root, group=root, owner can write, group can read, world can read). The following example shows the commands to use.

```
[ec2-user certs]$ sudo chown root:root intermediate.crt  
[ec2-user certs]$ sudo chmod 644 intermediate.crt  
[ec2-user certs]$ ls -al intermediate.crt
```

These commands should yield the following result.

```
-rw-r--r-- root root intermediate.crt
```

6. Place the private key that you used to create the CSR in the /etc/pki/tls/private/ directory.

 **Note**

There are several ways to upload your custom key to your EC2 instance, but the most straightforward and informative way is to open a text editor (for example, vi, nano, or notepad) on both your local computer and your instance, and then copy and paste the file contents between them. You need root [sudo] permissions when performing these operations on the EC2 instance. This way, you can see immediately if there are any permission or path problems. Be careful, however, not to add any additional lines while copying the contents, or to change them in any way.

From inside the /etc/pki/tls/private directory, use the following commands to verify that the file ownership, group, and permission settings match the highly restrictive AL2023 defaults (owner=root, group=root, read/write for owner only).

```
[ec2-user private]$ sudo chown root:root custom.key  
[ec2-user private]$ sudo chmod 600 custom.key  
[ec2-user private]$ ls -al custom.key
```

These commands should yield the following result.

```
-rw----- root root custom.key
```

7. Edit /etc/httpd/conf.d/ssl.conf to reflect your new certificate and key files.

- a. Provide the path and file name of the CA-signed host certificate in Apache's SSLCertificateFile directive:

```
SSLCertificateFile /etc/pki/tls/certs/custom.crt
```

- b. If you received an intermediate certificate file (`intermediate.crt` in this example), provide its path and file name using Apache's `SSLCACertificateFile` directive:

```
SSLCACertificateFile /etc/pki/tls/certs/intermediate.crt
```

 **Note**

Some CAs combine the host certificate and the intermediate certificates in a single file, making the `SSLCACertificateFile` directive unnecessary. Consult the instructions provided by your CA.

- c. Provide the path and file name of the private key (`custom.key` in this example) in Apache's `SSLCertificateKeyFile` directive:

```
SSLCertificateKeyFile /etc/pki/tls/private/custom.key
```

8. Save `/etc/httpd/conf.d/ssl.conf` and restart Apache.

```
[ec2-user ~]$ sudo systemctl restart httpd
```

9. Test your server by entering your domain name into a browser URL bar with the prefix `https://`. Your browser should load the test page over HTTPS without generating errors.

## Step 3: Test and harden the security configuration

After your TLS is operational and exposed to the public, you should test how secure it really is. This is easy to do using online services such as [Qualys SSL Labs](#), which performs a free and thorough analysis of your security setup. Based on the results, you may decide to harden the default security configuration by controlling which protocols you accept, which ciphers you prefer, and which you exclude. For more information, see [how Qualys formulates its scores](#).

 **Important**

Real-world testing is crucial to the security of your server. Small configuration errors may lead to serious security breaches and loss of data. Because recommended security practices

change constantly in response to research and emerging threats, periodic security audits are essential to good server administration.

On the [Qualys SSL Labs](#) site, enter the fully qualified domain name of your server, in the form `www.example.com`. After about two minutes, you receive a grade (from A to F) for your site and a detailed breakdown of the findings. The following table summarizes the report for a domain with settings identical to the default Apache configuration on AL2023, and with a default Certbot certificate.

Overall rating	B
Certificate	100%
Protocol support	95%
Key exchange	70%
Cipher strength	90%

Though the overview shows that the configuration is mostly sound, the detailed report flags several potential problems, listed here in order of severity:

- x The RC4 cipher is supported for use by certain older browsers.** A cipher is the mathematical core of an encryption algorithm. RC4, a fast cipher used to encrypt TLS data-streams, is known to have several [serious weaknesses](#). Unless you have very good reasons to support legacy browsers, you should disable this.
- x Old TLS versions are supported.** The configuration supports TLS 1.0 (already deprecated) and TLS 1.1 (on a path to deprecation). Only TLS 1.2 has been recommended since 2018.
- x Forward secrecy is not fully supported.** [Forward secrecy](#) is a feature of algorithms that encrypt using temporary (ephemeral) session keys derived from the private key. This means in practice that attackers cannot decrypt HTTPS data even if they possess a web server's long-term private key.

### To correct and future-proof the TLS configuration

1. Open the configuration file `/etc/httpd/conf.d/ssl.conf` in a text editor and comment out the following line by entering "#" at the beginning of the line.

```
#SSLProtocol all -SSLv3
```

## 2. Add the following directive:

```
#SSLProtocol all -SSLv3  
SSLProtocol -SSLv2 -SSLv3 -TLSv1 -TLSv1.1 +TLSv1.2
```

This directive explicitly disables SSL versions 2 and 3, as well as TLS versions 1.0 and 1.1. The server now refuses to accept encrypted connections with clients using anything except TLS 1.2. The verbose wording in the directive conveys more clearly, to a human reader, what the server is configured to do.

 **Note**

Disabling TLS versions 1.0 and 1.1 in this manner blocks a small percentage of outdated web browsers from accessing your site.

## To modify the list of allowed ciphers

1. In the configuration file `/etc/httpd/conf.d/ssl.conf`, find the section with the **SSLCipherSuite** directive and comment out the existing line by entering "#" at the beginning of the line.

```
#SSLCipherSuite HIGH:MEDIUM:!aNULL:!MD5
```

2. Specify explicit cipher suites and a cipher order that prioritizes forward secrecy and avoids insecure ciphers. The **SSLCipherSuite** directive used here is based on output from the [Mozilla SSL Configuration Generator](#), which tailors a TLS configuration to the specific software running on your server. (For more information, see Mozilla's useful resource [Security/Server Side TLS](#).) First determine your Apache and OpenSSL versions by using the output from the following commands.

```
[ec2-user ~]$ yum list installed | grep httpd
```

```
[ec2-user ~]$ yum list installed | grep openssl
```

For example, if the returned information is Apache 2.4.34 and OpenSSL 1.0.2, we enter this into the generator. If you choose the "modern" compatibility model, this creates an `SSLCipherSuite` directive that aggressively enforces security but still works for most browsers. If your software doesn't support the modern configuration, you can update your software or choose the "intermediate" configuration instead.

```
SSLCipherSuite ECDHE-ECDSA-AES256-GCM-SHA384:ECDHE-RSA-AES256-GCM-SHA384:ECDHE-  
ECDSA-CHACHA20-POLY1305:  
ECDHE-RSA-CHACHA20-POLY1305:ECDHE-ECDSA-AES128-GCM-SHA256:ECDHE-RSA-AES128-GCM-  
SHA256:  
ECDHE-ECDSA-AES256-SHA384:ECDHE-RSA-AES256-SHA384:ECDHE-ECDSA-AES128-SHA256:ECDHE-  
RSA-AES128-SHA256
```

The selected ciphers have *ECDHE* in their names, an abbreviation for *Elliptic Curve Diffie-Hellman Ephemeral*. The term *ephemeral* indicates forward secrecy. As a by-product, these ciphers do not support RC4.

We recommend that you use an explicit list of ciphers instead of relying on defaults or terse directives whose content isn't visible.

Copy the generated directive into `/etc/httpd/conf.d/ssl.conf`.

### Note

Though shown here on several lines for readability, the directive must be on a single line when copied to `/etc/httpd/conf.d/ssl.conf`, with only a colon (no spaces) between cipher names.

- Finally, uncomment the following line by removing the "#" at the beginning of the line.

```
#SSLHonorCipherOrder on
```

This directive forces the server to prefer high-ranking ciphers, including (in this case) those that support forward secrecy. With this directive turned on, the server tries to establish a strong secure connection before falling back to allowed ciphers with lesser security.

After completing both of these procedures, save the changes to /etc/httpd/conf.d/ssl.conf and restart Apache.

If you test the domain again on [Qualys SSL Labs](#), you should see that the RC4 vulnerability and other warnings are gone and the summary looks something like the following.

Overall rating	A
Certificate	100%
Protocol support	100%
Key exchange	90%
Cipher strength	90%

Each update to OpenSSL introduces new ciphers and removes support for old ones. Keep your EC2 AL2023 instance up-to-date, watch for security announcements from [OpenSSL](#), and be alert to reports of new security exploits in the technical press.

## Troubleshoot

- **My Apache webserver doesn't start unless I enter a password**

This is expected behavior if you installed an encrypted, password-protected, private server key.

You can remove the encryption and password requirement from the key. Assuming that you have a private encrypted RSA key called custom.key in the default directory, and that the password on it is **abcde12345**, run the following commands on your EC2 instance to generate an unencrypted version of the key.

```
[ec2-user ~]$ cd /etc/pki/tls/private/  
[ec2-user private]$ sudo cp custom.key custom.key.bak  
[ec2-user private]$ sudo openssl rsa -in custom.key -passin pass:abcde12345 -out  
custom.key.nocrypt  
[ec2-user private]$ sudo mv custom.key.nocrypt custom.key  
[ec2-user private]$ sudo chown root:root custom.key  
[ec2-user private]$ sudo chmod 600 custom.key  
[ec2-user private]$ sudo systemctl restart httpd
```

Apache should now start without prompting you for a password.

- **I get errors when I run sudo dnf install -y mod\_ssl.**

When you are installing the required packages for SSL, you may see errors similar to the following.

```
Error: httpd24-tools conflicts with httpd-tools-2.2.34-1.16.amzn1.x86_64  
Error: httpd24 conflicts with httpd-2.2.34-1.16.amzn1.x86_64
```

This typically means that your EC2 instance is not running AL2023. This tutorial only supports instances freshly created from an official AL2023 AMI.

## Tutorial: Host a WordPress blog on AL2023

The following procedures will help you install, configure, and secure a WordPress blog on your AL2023 instance. This tutorial is a good introduction to using Amazon EC2 in that you have full control over a web server that hosts your WordPress blog, which is not typical with a traditional hosting service.

You are responsible for updating the software packages and maintaining security patches for your server. For a more automated WordPress installation that does not require direct interaction with the web server configuration, the AWS CloudFormation service provides a WordPress template that can also get you started quickly. For more information, see [Get started in the AWS CloudFormation User Guide](#). If you'd prefer to host your WordPress blog on a Windows instance, see [Deploy a WordPress blog on your Amazon EC2 Windows instance](#) in the [Amazon EC2 User Guide](#). If you need a high-availability solution with a decoupled database, see [Deploying a high-availability WordPress website](#) in the [AWS Elastic Beanstalk Developer Guide](#).

### **Important**

These procedures are intended for use with AL2023. For information about other distributions, see their specific documentation. Many steps in this tutorial do not work on Ubuntu instances. For help installing WordPress on an Ubuntu instance, see [WordPress](#) in the Ubuntu documentation. You can also use [CodeDeploy](#) to accomplish this task on Amazon Linux, macOS, or Unix systems.

## Topics

- [Prerequisites](#)
- [Install WordPress](#)
- [Next steps](#)
- [Help! My public DNS name changed and now my blog is broken](#)

## Prerequisites

We strongly recommend that you associate an Elastic IP address (EIP) to the instance you are using to host a WordPress blog. This prevents the public DNS address for your instance from changing and breaking your installation. If you own a domain name and you want to use it for your blog, you can update the DNS record for the domain name to point to your EIP address (for help with this, contact your domain name registrar). You can have one EIP address associated with a running instance at no charge. For more information, see [Elastic IP addresses](#) in the *Amazon EC2 User Guide*. The [Tutorial: Install a LAMP server on AL2023](#) tutorial has steps for configuring a security group to allow HTTP and HTTPS traffic, as well as several steps to ensure that file permissions are set properly for your web server. For information about adding rules to your security group, see [Add rules to a security group](#).

If you don't already have a domain name for your blog, you can register a domain name with Route 53 and associate your instance's EIP address with your domain name. For more information, see [Registering domain names using Amazon Route 53](#) in the *Amazon Route 53 Developer Guide*.

## Install WordPress

Connect to your instance, and download the WordPress installation package. For more information about connecting to your instance, see [Connecting to AL2023 instances](#).

1. Download and install these packages using the following command.

```
dnf install wget php-mysqlnd httpd php-fpm php-mysqli mariadb105-server php-json  
php php-devel -y
```

2. You may notice a warning displayed with similar verbiage in the output (the versions may vary over time):

**WARNING:**

```
A newer release of "Amazon Linux" is available.
```

Available Versions:

```
dnf update --releasever=2023.0.20230202
```

Release notes:

```
https://aws.amazon.com
```

Version 2023.0.20230204:

Run the following command to update to 2023.0.20230204:

```
dnf update --releasever=2023.0.20230204 ... etc
```

As a best-practice we recommend keeping the OS as up-to-date as possible, but you may want to iterate through each version to ensure there are no conflicts in your environment. **If installation of the preceding packages noted in step 1 fail, you may need to update to one of the newer releases listed, and retry.**

3. Download the latest WordPress installation package with the `wget` command. The following command should always download the latest release.

```
[ec2-user ~]$ wget https://wordpress.org/latest.tar.gz
```

4. Unzip and unarchive the installation package. The installation folder is unzipped to a folder called `wordpress`.

```
[ec2-user ~]$ tar -xzf latest.tar.gz
```

## To create a database user and database for your WordPress installation

Your WordPress installation needs to store information, such as blog posts and user comments, in a database. This procedure helps you create your blog's database and a user that is authorized to read and save information to it.

1. Start the database and web server.

```
[ec2-user ~]$ sudo systemctl start mariadb httpd
```

2. Log in to the database server as the `root` user. Enter your database `root` password when prompted; this may be different than your `root` system password, or it might even be empty if you have not secured your database server.

If you have not secured your database server yet, it is important that you do so. For more information, see [Step 3: Secure the database server \(AL2023\)](#).

```
[ec2-user ~]$ mysql -u root -p
```

3. Create a user and password for your MySQL database. Your WordPress installation uses these values to communicate with your MySQL database. Enter the following command, substituting a unique user name and password.

```
CREATE USER 'wordpress-user'@'localhost' IDENTIFIED BY 'your_strong_password';
```

Make sure that you create a strong password for your user. Do not use the single quote character ( ' ) in your password, because this will break the preceding command. Do not reuse an existing password, and make sure to store this password in a safe place.

4. Create your database. Give your database a descriptive, meaningful name, such as `wordpress-db`.

 **Note**

The punctuation marks surrounding the database name in the command below are called backticks. The backtick ( ` ) key is usually located above the Tab key on a standard keyboard. Backticks are not always required, but they allow you to use otherwise illegal characters, such as hyphens, in database names.

```
CREATE DATABASE `wordpress-db`;
```

5. Grant full privileges for your database to the WordPress user that you created earlier.

```
GRANT ALL PRIVILEGES ON `wordpress-db`.* TO "wordpress-user"@"localhost";
```

6. Flush the database privileges to pick up all of your changes.

```
FLUSH PRIVILEGES;
```

## 7. Exit the mysql client.

```
exit
```

### To create and edit the wp-config.php file

The WordPress installation folder contains a sample configuration file called wp-config-sample.php. In this procedure, you copy this file and edit it to fit your specific configuration.

1. Copy the wp-config-sample.php file to a file called wp-config.php. This creates a new configuration file and keeps the original sample file intact as a backup.

```
[ec2-user ~]$ cp wordpress/wp-config-sample.php wordpress/wp-config.php
```

2. Edit the wp-config.php file with your favorite text editor (such as **nano** or **vim**) and enter values for your installation. If you do not have a favorite text editor, nano is suitable for beginners.

```
[ec2-user ~]$ nano wordpress/wp-config.php
```

- a. Find the line that defines DB\_NAME and change database\_name\_here to the database name that you created in [Step 4 of To create a database user and database for your WordPress installation.](#)

```
define('DB_NAME', 'wordpress-db');
```

- b. Find the line that defines DB\_USER and change username\_here to the database user that you created in [Step 3 of To create a database user and database for your WordPress installation.](#)

```
define('DB_USER', 'wordpress-user');
```

- c. Find the line that defines DB\_PASSWORD and change password\_here to the strong password that you created in [Step 3 of To create a database user and database for your WordPress installation.](#)

```
define('DB_PASSWORD', 'your_strong_password');
```

- d. Find the section called Authentication Unique Keys and Salts. These KEY and SALT values provide a layer of encryption to the browser cookies that WordPress users store on their local machines. Basically, adding long, random values here makes your site more secure. Visit <https://api.wordpress.org/secret-key/1.1/salt/> to randomly generate a set of key values that you can copy and paste into your wp-config.php file. To paste text into a PuTTY terminal, place the cursor where you want to paste the text and right-click your mouse inside the PuTTY terminal.

For more information about security keys, go to <https://wordpress.org/support/article/editing-wp-config-php/#security-keys>.

 **Note**

The values below are for example purposes only; do not use these values for your installation.

```
define('AUTH_KEY',           '#U$$+[RXN8:b^-L_0(WU_+ c+wFkI~c]o]-bHw+)/
Aj[wTwSiz<Qb[mghEXcRh-');
define('SECURE_AUTH_KEY',    'Zsz._P=l/|y.Lq)Xjlkws1y5NJ76E6EJ.AV0pCKZZB,*~*r ?
60P$eJT@;+(ndLg');
define('LOGGED_IN_KEY',      'ju}qwre3V*+8f_z0WF?{LlGsQ]Ye@2Jh^,8x>)Y |;(^[Iw]Pi
+LG#A4R?7N`YB3');
define('NONCE_KEY',          'P(g62HeZxEes/LnI^i=H,[XwK9I&[2s/:?0N]VJM%?;v2v]v+;
+^9eXUahg@::Cj');
define('AUTH_SALT',           'C$DpB4Hj[JK:?:qL`sRVa:{:7yShy(9A@5wg+'JJVb1fk%-
Bx*M4(qc[Qg%JT!h');
define('SECURE_AUTH_SALT',   'd!uRu#+q#{f$Z?Z9uFPG.${+S{n~1M&%@~gL>U>NV<zpD-@2-
Es7Q10-bp28EKv');
define('LOGGED_IN_SALT',     'j{00P*owZf)kVD+FVLn-~ >. |Y%Ug4#I^*LVd9QeZ^&XmK|
e(76mic+&W&+^0P/');
define('NONCE_SALT',         '-97r*V/cgxLmp?Zy4zUU4r99QQ_rGs2LTd%P; |
_e1tS)8_B/, .6[=UK<]_y9?JWG');
```

- e. Save the file and exit your text editor.

## To install your WordPress files under the Apache document root

- Now that you've unzipped the installation folder, created a MySQL database and user, and customized the WordPress configuration file, you are ready to copy your installation files to your web server document root so you can run the installation script that completes your installation. The location of these files depends on whether you want your WordPress blog to be available at the actual root of your web server (for example, *my.public.dns.amazonaws.com*) or in a subdirectory or folder under the root (for example, *my.public.dns.amazonaws.com/blog*).
  - If you want WordPress to run at your document root, copy the contents of the `wordpress` installation directory (but not the directory itself) as follows:

```
[ec2-user ~]$ cp -r wordpress/* /var/www/html/
```

- If you want WordPress to run in an alternative directory under the document root, first create that directory, and then copy the files to it. In this example, WordPress will run from the directory `blog`:

```
[ec2-user ~]$ mkdir /var/www/html/blog  
[ec2-user ~]$ cp -r wordpress/* /var/www/html/blog/
```

### Important

For security purposes, if you are not moving on to the next procedure immediately, stop the Apache web server (`httpd`) now. After you move your installation under the Apache document root, the WordPress installation script is unprotected and an attacker could gain access to your blog if the Apache web server were running. To stop the Apache web server, enter the command **`sudo service httpd stop`**. If you are moving on to the next procedure, you do not need to stop the Apache web server.

## To allow WordPress to use permalinks

WordPress permalinks need to use Apache `.htaccess` files to work properly, but this is not enabled by default on Amazon Linux. Use this procedure to allow all overrides in the Apache document root.

1. Open the `httpd.conf` file with your favorite text editor (such as **nano** or **vim**). If you do not have a favorite text editor, **nano** is suitable for beginners.

```
[ec2-user ~]$ sudo vim /etc/httpd/conf/httpd.conf
```

2. Find the section that starts with `<Directory "/var/www/html">`.

```
<Directory "/var/www/html">
#
# Possible values for the Options directive are "None", "All",
# or any combination of:
#   Indexes Includes FollowSymLinks SymLinksIfOwnerMatch ExecCGI MultiViews
#
# Note that "MultiViews" must be named *explicitly* --- "Options All"
# doesn't give it to you.
#
# The Options directive is both complicated and important. Please see
# http://httpd.apache.org/docs/2.4/mod/core.html#options
# for more information.
#
Options Indexes FollowSymLinks

#
# AllowOverride controls what directives may be placed in .htaccess files.
# It can be "All", "None", or any combination of the keywords:
#   Options FileInfo AuthConfig Limit
#
AllowOverride None

#
# Controls who can get stuff from this server.
#
Require all granted
</Directory>
```

3. Change the `AllowOverride None` line in the above section to read `AllowOverride All`.

 **Note**

There are multiple `AllowOverride` lines in this file; be sure you change the line in the `<Directory "/var/www/html">` section.

```
AllowOverride All
```

4. Save the file and exit your text editor.

## To install the PHP graphics drawing library on AL2023

The GD library for PHP enables you to modify images. Install this library if you need to crop the header image for your blog. The version of phpMyAdmin that you install might require a specific minimum version of this library (for example, version 8.1).

Use the following command to install the PHP graphics drawing library on AL2023. For example, if you installed php8.1 from source as part of installing the LAMP stack, this command installs version 8.1 of the PHP graphics drawing library.

```
[ec2-user ~]$ sudo dnf install php-gd
```

To verify the installed version, use the following command:

```
[ec2-user ~]$ sudo dnf list installed | grep php-gd
```

The following is example output:

php-gd.x86_64	8.1.30-1.amzn2	@amazonlinux
---------------	----------------	--------------

## To install the PHP graphics drawing library on the Amazon Linux AMI

The GD library for PHP enables you to modify images. Install this library if you need to crop the header image for your blog. The version of phpMyAdmin that you install might require a specific minimum version of this library (for example, version 8.1).

To verify which versions are available, use the following command:

```
[ec2-user ~]$ dnf list | grep php
```

The following is example lines from the output for the PHP graphics drawing library (version 8.1):

php8.1.aarch64	8.1.7-1.amzn2023.0.1
	@amazonlinux

php8.1-cli.aarch64	@amazonlinux	8.1.7-1.amzn2023.0.1
php8.1-common.aarch64	@amazonlinux	8.1.7-1.amzn2023.0.1
php8.1-devel.aarch64	@amazonlinux	8.1.7-1.amzn2023.0.1
php8.1-fpm.aarch64	@amazonlinux	8.1.7-1.amzn2023.0.1
php8.1-gd.aarch64	@amazonlinux	8.1.7-1.amzn2023.0.1

Use the following command to install a specific version of the PHP graphics drawing library (for example, version php8.1) on the Amazon Linux AMI:

```
[ec2-user ~]$ sudo dnf install -y php8.1-gd
```

## To fix file permissions for the Apache web server

Some of the available features in WordPress require write access to the Apache document root (such as uploading media through the Administration screens). If you have not already done so, apply the following group memberships and permissions (as described in greater detail in the [LAMP web server tutorial](#)).

1. Grant file ownership of /var/www and its contents to the apache user.

```
[ec2-user ~]$ sudo chown -R apache /var/www
```

2. Grant group ownership of /var/www and its contents to the apache group.

```
[ec2-user ~]$ sudo chgrp -R apache /var/www
```

3. Change the directory permissions of /var/www and its subdirectories to add group write permissions and to set the group ID on future subdirectories.

```
[ec2-user ~]$ sudo chmod 2775 /var/www
[ec2-user ~]$ find /var/www -type d -exec sudo chmod 2775 {} \;
```

4. Recursively change the file permissions of /var/www and its subdirectories.

```
[ec2-user ~]$ find /var/www -type f -exec sudo chmod 0644 {} \;
```

**Note**

If you intend to also use WordPress as an FTP server, you'll need more permissive Group settings here. Please review the recommended [steps and security settings in WordPress](#) to accomplish this.

5. Restart the Apache web server to pick up the new group and permissions.

```
[ec2-user ~]$ sudo systemctl restart httpd
```

### To run the WordPress installation script with AL2023

You are ready to install WordPress. The commands that you use depend on the operating system. The commands in this procedure are for use with AL2023. Use the procedure that follows this one with AL2023 AMI.

1. Use the **systemctl** command to ensure that the httpd and database services start at every system boot.

```
[ec2-user ~]$ sudo systemctl enable httpd && sudo systemctl enable mariadb
```

2. Verify that the database server is running.

```
[ec2-user ~]$ sudo systemctl status mariadb
```

If the database service is not running, start it.

```
[ec2-user ~]$ sudo systemctl start mariadb
```

3. Verify that your Apache web server (httpd) is running.

```
[ec2-user ~]$ sudo systemctl status httpd
```

If the httpd service is not running, start it.

```
[ec2-user ~]$ sudo systemctl start httpd
```

4. In a web browser, type the URL of your WordPress blog (either the public DNS address for your instance, or that address followed by the blog folder). You should see the WordPress installation script. Provide the information required by the WordPress installation. Choose **Install WordPress** to complete the installation. For more information, see [Step 5: Run the Install Script](#) on the WordPress website.

## To run the WordPress installation script with AL2023 AMI

1. Use the **chkconfig** command to ensure that the httpd and database services start at every system boot.

```
[ec2-user ~]$ sudo chkconfig httpd on && sudo chkconfig mariadb on
```

2. Verify that the database server is running.

```
[ec2-user ~]$ sudo service mariadb status
```

If the database service is not running, start it.

```
[ec2-user ~]$ sudo service mariadb start
```

3. Verify that your Apache web server (httpd) is running.

```
[ec2-user ~]$ sudo service httpd status
```

If the httpd service is not running, start it.

```
[ec2-user ~]$ sudo service httpd start
```

4. In a web browser, type the URL of your WordPress blog (either the public DNS address for your instance, or that address followed by the blog folder). You should see the WordPress installation script. Provide the information required by the WordPress installation. Choose **Install WordPress** to complete the installation. For more information, see [Step 5: Run the Install Script](#) on the WordPress website.

## Next steps

After you have tested your WordPress blog, consider updating its configuration.

## Use a custom domain name

If you have a domain name associated with your EC2 instance's EIP address, you can configure your blog to use that name instead of the EC2 public DNS address. For more information, see [Changing The Site URL](#) on the WordPress website.

## Configure your blog

You can configure your blog to use different [themes](#) and [plugins](#) to offer a more personalized experience for your readers. However, sometimes the installation process can backfire, causing you to lose your entire blog. We strongly recommend that you create a backup Amazon Machine Image (AMI) of your instance before attempting to install any themes or plugins so you can restore your blog if anything goes wrong during installation. For more information, see [Create your own AMI](#) in the *Amazon EC2 User Guide*.

## Increase capacity

If your WordPress blog becomes popular and you need more compute power or storage, consider the following steps:

- Expand the storage space on your instance. For more information, see [Amazon EBS Elastic Volumes](#).
- Move your MySQL database to [Amazon RDS](#) to take advantage of the service's ability to scale easily.

## Improve network performance of your internet traffic

If you expect your blog to drive traffic from users located around the world, consider [AWS Global Accelerator](#). Global Accelerator helps you achieve lower latency by improving internet traffic performance between your users' client devices and your WordPress application running on AWS. Global Accelerator uses the [AWS global network](#) to direct traffic to a healthy application endpoint in the AWS Region that is closest to the client.

## Learn more about WordPress

The following links contain more information about WordPress.

- For information about WordPress, see the WordPress Codex help documentation at [Codex](#).
- For more information about troubleshooting your installation, go to [Common installation problems](#).

- For information about making your WordPress blog more secure, go to [Hardening WordPress](#).
- For information about keeping your WordPress blog up-to-date, go to [Updating WordPress](#).

## Help! My public DNS name changed and now my blog is broken

Your WordPress installation is automatically configured using the public DNS address for your EC2 instance. If you stop and restart the instance, the public DNS address changes (unless it is associated with an Elastic IP address) and your blog will not work anymore because it references resources at an address that no longer exists (or is assigned to another EC2 instance). A more detailed description of the problem and several possible solutions are outlined in <https://wordpress.org/support/article/changing-the-site-url/>.

If this has happened to your WordPress installation, you may be able to recover your blog with the procedure below, which uses the `wp-cli` command line interface for WordPress.

### To change your WordPress site URL with the wp-cli

1. Connect to your EC2 instance with SSH.
2. Note the old site URL and the new site URL for your instance. The old site URL is likely the public DNS name for your EC2 instance when you installed WordPress. The new site URL is the current public DNS name for your EC2 instance. If you are not sure of your old site URL, you can use `curl` to find it with the following command.

```
[ec2-user ~]$ curl localhost | grep wp-content
```

You should see references to your old public DNS name in the output, which will look like this (old site URL in red):

```
<script type='text/javascript' src='http://ec2-52-8-139-223.us-west-1.compute.amazonaws.com/wp-content/themes/twentyfifteen/js/functions.js?ver=20150330'></script>
```

3. Download the `wp-cli` with the following command.

```
[ec2-user ~]$ curl -O https://raw.githubusercontent.com/wp-cli/builds/gh-pages/phar/wp-cli.phar
```

4. Search and replace the old site URL in your WordPress installation with the following command. Substitute the old and new site URLs for your EC2 instance and the path to your WordPress installation (usually /var/www/html or /var/www/html/blog).

```
[ec2-user ~]$ php wp-cli.phar search-replace 'old_site_url' 'new_site_url' --path=/  
path/to/wordpress/installation --skip-columns=guid
```

5. In a web browser, enter the new site URL of your WordPress blog to verify that the site is working properly again. If it is not, see [Changing the site URL](#) and [Common installation problems](#) for more information.

# Using Amazon Linux 2023 outside of Amazon EC2

The Amazon Linux 2023 container images can be run in compatible container runtime environments. For more information on how to use Amazon Linux 2023 inside a container, see [AL2023 in containers](#).

Amazon Linux 2023 (AL2023) can also be run as a virtualized guest outside of directly being run on Amazon EC2. There are currently KVM (qcow2), VMware (OVA), and Hyper-V (vhdx) images available.

 **Note**

The configuration of Amazon Linux 2023 images differs from Amazon Linux 2.

If you are coming from [Running Amazon Linux 2 as a virtual machine on premises](#) you will need to adapt your configuration to be compatible with AL2023.

## Download Amazon Linux 2023 images for use with KVM, VMware, and Hyper-V

Amazon Linux 2023 disk images for use with KVM, VMware, and Hyper-V can be downloaded from [cdn.amazonlinux.com](#).

## Supported configurations of Amazon Linux 2023 for use in non-Amazon EC2 virtualized environments

This section covers the requirements for running Amazon Linux 2023 in non-Amazon EC2 virtualized environments such as on KVM, VMware, or and Hyper-V.

The base [AL2023 system requirements](#) apply to all non-Amazon EC2 virtualized environments. A list of supported device models is detailed for each hypervisor environment in the following topics.

KVM, VMware, and Hyper-V provide many configuration options, and care needs to be taken in order to configure them for your security, performance, and reliability needs. For more information, check the documentation provided by your hypervisor.

## Topics

- [Requirements for running AL2023 on KVM](#)
- [Requirements for running AL2023 on VMware](#)
- [Requirements for running Amazon Linux 2023 on Hyper-V](#)

## Requirements for running AL2023 on KVM

This section describes the requirements for running AL2023 on KVM. The KVM images of AL2023 are available for both aarch64 and x86-64 architectures. These requirements are in addition to the base [AL2023 system requirements](#) for the KVM images.

## Topics

- [KVM host requirements for running AL2023 on KVM](#)
- [Device support for AL2023 on KVM](#)
- [Boot mode \(UEFI and BIOS\) support for AL2023 on KVM](#)
- [Limitations running AL2023 on KVM](#)

## KVM host requirements for running AL2023 on KVM

The KVM images are currently qualified on a host running Ubuntu 22.04.3 LTS with qemu version 6.2+dfsg-2ubuntu6.15, provided by this Ubuntu version, using a q35 machine type for x86-64 and a virt machine type for aarch64.

## Device support for AL2023 on KVM

**The qemu device models tested for use with AL2023 KVM images (both aarch64 and x86-64) are:**

- `virtio-blk` (virtio block device)
- `virtio-scsi` (virtio SCSI controller with disk device)
- `virtio-net` (virtio network device)
- `ahci` (for use with the virtual CD-ROM drive)
- `usb-storage` (over `xhci`)

## Additional qemu device models enabled in AL2023 KVM image qualification, but not heavily exercised are:

- VGA (qemu VGA) on x86-64 only
- virtio-rng (virtual random number generator)
- legacy AT keyboard and PS/2 mouse devices
- legacy serial device

## Boot mode (UEFI and BIOS) support for AL2023 on KVM

The x86-64 image is tested with both legacy BIOS and UEFI boot modes. The aarch64 images are tested with UEFI boot mode.

### Note

By default, when using UEFI boot mode, some virtual machine managers will provision the VM with Microsoft Secure Boot keys which enables Secure Boot. This configuration will not boot AL2023.

Because the AL2023 boot loader isn't signed by Microsoft, the VM must be provisioned either without UEFI keys, or with the AL2023 keys for Secure Boot.

### Important

Secure Boot support for KVM images has not been validated yet.

## Limitations running AL2023 on KVM

There are some known limitations in running AL2023 on KVM.

### Note

Code implementing some of the listed unsupported functionality might exist in AL2023 and function correctly. The list of unsupported functionality exists so that you can make informed decisions about what to rely upon working today, and what the Amazon Linux team will qualify as working as part of future updates.

## Known Limitations with running AL2023 on KVM

- The KVM guest agent is not currently packaged or supported.
- Hot plugging and unplugging CPU, memory, or any other device type is not supported.
- VM hibernation is not supported.
- VM migration is not supported.
- Passthrough of any device such as through PCI Passthrough, or USB Passthrough is not supported.

## Requirements for running AL2023 on VMware

This section describes the requirements for running AL2023 on VMware. The VMware images of AL2023 are available for only the x86-64 architecture. VMware images for aarch64 are not available or supported. These requirements are in addition to the base [AL2023 system requirements](#) for the VMware images.

### Topics

- [VMware host requirements for running AL2023 on VMware](#)
- [Device support for AL2023 on VMware](#)
- [Boot mode \(UEFI and BIOS\) support for AL2023 on VMware](#)
- [Limitations running AL2023 on VMware](#)

## VMware host requirements for running AL2023 on VMware

The AL2023 VMware OVA images are currently qualified on the following:

- VMware Workstation 17.5.0 running on hosts using an Intel(R) Xeon(R) Platinum 8124M processor
- VMware vSphere 8.0 using an Intel(R) Xeon(R) Platinum 8275CL processor

The AL2023 VMware OVA images specify a *Machine Hardware Version* of 13.

**VMware Machine Hardware Version 13 is supported by:**

- ESXi 6.5 or later

- VMware Workstation 14 or later

## Device support for AL2023 on VMware

**The following VMware device models were tested for use with AL2023 VMware OVA images (x86-64 only):**

- `vmw_pvscsi` (VMware paravirtualized SCSI controller)
- `vmxnet3` (VMware paravirtualized network device)
- `ata_piix` (legacy IDE for use with the virtual CD-ROM drive only)

**Additional VMware device models enabled in AL2023 VMware image qualification, but not heavily exercised:**

- `vmw_vmc1` and related vsock interface (virtual socket transport for the VMware guest agent)
- `vmw_balloon` memory balloon device
- VMware SVGA controller
- legacy AT keyboard and PS/2 mouse devices

The VMware guest agent package (`open-vm-tools`) is available and installed by default in the AL2023 VMware OVA images.

## Boot mode (UEFI and BIOS) support for AL2023 on VMware

As of the 2023.3.20231211 release, the AL2023 VMware OVA image has been validated in both legacy BIOS and UEFI boot modes. The OVA default configuration is still legacy BIOS but can be changed by the user.

**A** **Important**

Secure Boot support requires UEFI, which has not been validated for AL2023 running on VMware.

## Limitations running AL2023 on VMware

There are some known limitations in running AL2023 on VMware.

**Note**

Code implementing some of the listed unsupported functionality may exist in AL2023 and function correctly. The list of unsupported functionality exists so that customers can make informed decisions about what to rely upon working today, and what the Amazon Linux team will qualify as working as part of future updates.

## Known limitations with running AL2023 on VMware

- UEFI Secure Boot is not currently validated with AL2023 on VMware.
- Hot plugging and unplugging CPU, memory, or any other device type is not supported.
- VM hibernation is not supported.
- VM migration is not supported.
- Passthrough of any device such as through PCI Passthrough, or USB Passthrough is not supported.

## Requirements for running Amazon Linux 2023 on Hyper-V

This section covers the requirements for running Amazon Linux 2023 on Hyper-V. The Hyper-V images of AL2023 are available only for the x86-64 architecture. Hyper-V images for aarch64 are not available or supported at this time.

This section covers additional requirements on top of the base [AL2023 system requirements](#) for the Hyper-V images.

### Topics

- [Hyper-V host requirements for running Amazon Linux 2023 on Hyper-V](#)
- [Device support for Amazon Linux 2023 on Hyper-V](#)
- [Limitations running Amazon Linux 2023 on Hyper-V](#)

## Hyper-V host requirements for running Amazon Linux 2023 on Hyper-V

The main qualification of Amazon Linux 2023 on Hyper-V happens on Windows Server 2022 running on an EC2 c5.metal instance.

## Device support for Amazon Linux 2023 on Hyper-V

Amazon Linux 2023 is tested on both *Generation 1* and *Generation 2* Hyper-V virtual machines with the following set of virtualized hardware:

- Generation 1 (legacy BIOS boot) VM
- Generation 2 (UEFI boot - No secure boot) VM
- The following device models are tested for use with AL2023 Hyper-V images:
  - Hyper-V virtual storage `hv_storvsc` for the root disk and the emulated CD-ROM drive on *Generation 2* VMs
  - Emulated PIIX IDE `ata_piix` for the virtual CD-ROM drive on *Generation 1* VMs
  - Hyper-V virtual ethernet `hv_netvsc`
- The following device models are enabled but lightly tested:
  - Legacy VGA text mode on *Generation 1* VMs
  - UEFI Firmware based framebuffer `simpledrmfb` on *Generation 2* VMs
  - Hyper-V Balloon `hv_balloon`
  - Hyper-V Balloon `hv_balloon`
  - Hyper-V HID/Mouse `hid_hyperv`
- The following device modes are *not* enabled in AL2023 at this time:
  - Hyper-V PCI pass-through
  - Hyper-V DRM Graphics

### Important

For *Generation 2* virtual machines, Secure Boot is not supported and must be disabled prior to launching the virtual machine for a successful boot of Amazon Linux 2023. Hyper-V currently only supports Secure Boot with software components signed by Microsoft's own keys while the Amazon Linux bootloader is signed by an Amazon private key. Hyper-V doesn't support importing 3rd party keys at this point.

## Limitations running Amazon Linux 2023 on Hyper-V

The following are some known limitations in running Amazon Linux 2023 on Hyper-V:

**Note**

Code implementing some of the listed unsupported functionality may exist in AL2023 and function correctly. The list of unsupported functionality exists so that customers can make informed decisions about what to rely upon working today, and what the Amazon Linux team will qualify as working as part of future updates.

## Known Limitations with running AL2023 on Hyper-V

- UEFI Secure Boot mode is not currently supported nor functional with AL2023 on Hyper-V
- Hot plugging and unplugging CPU, memory, or any other device type is not supported.
- Virtual Machine (VM) hibernation is not supported.
- Virtual Machine (VM) migration is not supported.
- Passthrough of any device such as through PCI Passthrough, or USB Passthrough is not supported.

## Amazon Linux 2023 Set up and cloud-init configuration when used outside Amazon EC2

This section covers how to set up and configure a Amazon Linux 2023 virtual machine when not run directly on Amazon EC2, such as when on KVM, VMware, or Hyper-V.

By default, an Amazon Linux 2023 virtual machine images don't come provisioned with any user password or ssh key and will obtain its network configuration via DHCP on the first discovered network interface. This means that by default, without additional configuration, there is no way to connect to the resulting virtual machine.

Thus, some form of configuration needs to be provided to the virtual machine. The standard mechanism to do this for Amazon Linux is via `cloud-init` data sources.

Amazon Linux 2023 has been qualified with the following data sources:

### NoCloud

This is the traditional method of configuring on-premises images via a virtual CD-ROM containing a seed ISO9660 image with `cloud-init` configuration files.

## VMware

Amazon Linux 2023 additionally supports configuring VMware images running on vSphere via the VMware specific data source via VMware guestinfo.userdata and guestinfo.metadata.

### Note

The configuration of the data sources can differ from Amazon Linux 2. More specifically, Amazon Linux 2023 uses systemd-networkd for its configuration and requires the use of cloud-init "Networking Config Version 2" as documented in [the cloud-init network configuration documentation](#).

The complete documentation for cloud-init configuration mechanisms for the version of cloud-init packaged in Amazon Linux 2023 can be found in the [upstream cloud-init documentation](#).

## NoCloud (`seed.iso`) cloud-init configuration for Amazon Linux 2023 on KVM and VMware

This section covers how to create and use a `seed.iso` image to configure Amazon Linux 2023 running on KVM or VMware. Because KVM and VMware environments do not have [Amazon EC2 Instance Meta Data Service \(IMDS\)](#), an alternate method of configuring Amazon Linux 2023 is required, and providing a `seed.iso` image is one of those methods.

The `seed.iso` boot image includes the initial configuration information that is needed to boot and configure your new virtual machine, such as the network configuration, host name, and user data.

### Note

The `seed.iso` image includes only the configuration information required to boot the VM. It does not include the Amazon Linux 2023 operating system files.

To generate the `seed.iso` image, you need at least two configuration files, sometimes three:

## meta-data

This file typically includes the hostname for the virtual machine.

## user-data

This file typically configures user accounts, their passwords, ssh key pairs, and/or access mechanisms. By default, the Amazon Linux 2023 KVM and VMware images create an `ec2-user` user account. You can use the `user-data` configuration file to set the password and/or ssh keys for this default user account.

## network-config (optional)

This file typically provides a network configuration for the virtual machine which will override the default one. The default configuration is to use DHCP on the first available network interface.

## Create the seed.iso disk image

1. On a Linux or macOS computer, create a new folder named `seedconfig` and navigate into it.

 **Note**

Using Windows or another Operating System to complete these steps is possible, but you will have to find the equivalent tool to `mkisofs` to complete creating the `seed.iso` image.

2. Create the meta-data configuration file.

- a. Create a new file named `meta-data`.
- b. Open the `meta-data` file using your preferred editor and add the following, replacing `vm-hostname` with the host name for the VM:

```
local-hostname: vm-hostname
```

- c. Save and close the `meta-data` configuration file.

3. Create the `user-data` configuration file.

- a. Create a new file named `user-data`.

- b. Open the user-data file using your preferred editor and add the following, making substitutions as needed:

```
#cloud-config
#vim:syntax=yaml
users:
  # A user by the name 'ec2-user' is created in the image by default.
  - default
  - name: ec2-user
    ssh_authorized_keys:
      - ssh-rsa ssh-key
    # In the above line, replace ssh key with the content of your ssh public key.
```

- c. You can optionally add more user accounts to the user-data configuration file.

You can specify additional user accounts, their access mechanisms, passwords, and key pairs. For more information about the supported directives, see the [upstream cloud-init documentation](#).

- d. Save and close the user-data configuration file.

4. (Optional) Create the network-config configuration file.

- a. Create a new file named network-config.
- b. Open the network-config file using your preferred editor and add the following, replacing the various IP addresses with the appropriate ones for your setup.

```
version: 2
ethernets:
  enp1s0:
    addresses:
      - 192.168.122.161/24
    gateway4: 192.168.122.1
    nameservers:
      addresses: 192.168.122.1
```

**Note**

cloud-init network configuration provides mechanisms to match against the MAC address of the interface instead of specifying the interface name which can change depending on the VM configuration. This (and more) cloud-init features for network configuration are described in more detail in the [upstream cloud-init Network Config Version 2 documentation](#).

- c. Save and close the network-config configuration file.
5. Create the seed.iso disk image using the meta-data, user-data, and optional network-config configuration files created in the previous steps.

Do one of the following, depending on the OS you are creating the seed.iso disk image on.

- On Linux systems, use a tool such as **mkisofs** or **genisoimage** to create the completed seed.iso file. Navigate into the seedconfig folder, and run the following command:

```
$ mkisofs -output seed.iso -volid cidata -joliet -rock user-data meta-data
```

- If you use a network-config, include it in the invocation of **mkisofs**:

```
$ mkisofs -output seed.iso -volid cidata -joliet -rock user-data meta-data  
network-config
```

- On macOS systems, you can use a tool such as **hdiutil** to generate the finished seed.iso file. Since **hdiutil** takes a pathname rather than a list of files, the same invocation can be used regardless of if a network-config configuration file has been created or not.

```
$ hdiutil makehybrid -o seed.iso -hfs -joliet -iso -default-volume-name cidata  
seedconfig/
```

6. The resulting seed.iso file can now be attached to your new Amazon Linux 2023 Virtual Machine via a virtual CD-ROM drive for cloud-init to find on first boot and apply the configuration to the system.

# VMware guestinfo cloud-init configuration for AL2023 on VMware

VMware environments do not have the [Amazon EC2 Instance Meta Data Service \(IMDS\)](#), so an alternate method of configuring AL2023 is required. This section describes how to use an alternative configuration mechanism to the seed.iso virtual CD-ROM drive that is available in VMware vSphere.

This method of configuration uses the VMware extraconfig mechanism to provide configuration data to cloud-init. For each of the following keys, a corresponding **keyname.encoding** property must be provided.

The following keys can be provided to the VMware extraconfig mechanism.

## **guestinfo.metadata**

JSON or YAML containing cloud-init meta-data

## **guestinfo.userdata**

A YAML document containing cloud-init user-data in the cloud-config format.

## **guestinfo.vendordata (optional)**

YAML containing cloud-init vendor-data

The corresponding encoding properties (`guestinfo.metadata.encoding`, `guestinfo.userdata.encoding`, and `guestinfo.vendordata.encoding`) can contain:

### **base64**

The content of the property is base64 encoded.

### **gzip+base64**

The content of the property is compressed with gzip after base64 encoding.

#### **Note**

The seed.iso method supports a separate (optional) network-config configuration file. VMware guestinfo differs in how the networking configuration is provided. Additional information is provided in the following section.

If an explicit network configuration is desired, it should be embedded in the metadata in the form of two YAML or JSON properties:

## network

Contains the encoded network configuration in JSON or YAML form.

## network.encoding

Contains the encoding of the above network configuration data. The cloud-init supported encodings are the same as for the guestinfo data: base64 and gzip+base64.

## Example Using the VMware vSphere govc CLI tool to pass configuration with guestinfo

1. Prepare the meta-data, user-data, and optional network-config configuration files as described in [NoCloud \(seed.iso\) cloud-init configuration for Amazon Linux 2023 on KVM and VMware](#).
2. Convert the configuration files into formats usable by VMware guestinfo.

```
# 'meta-data', `user-data` and `network-config` are the configuration
# files in the same format that would be used by a NoCloud (seed.iso)
# data source, read-them and convert them to VMware guestinfo
#
# The VM_NAME variable is assumed to be set to the name of the VM
# It is assumed that the necessary govc environment (credentials etc...) are
# already set

metadata=$(cat "meta-data")
userdata=$(cat "user-data")
if [ -e "network-config" ] ; then
    # We need to embed the network config inside the meta-data
    netconf=$(base64 -w0 "network-config")
    metadata=$(printf "%s\nnetwork: %s\nnetwork.encoding: base64" "$metadata"
"$netconf")
fi
metadata=$(base64 -w0 <<< "$metadata")
govc vm.change -vm "$VM_NAME" \
-e guestinfo.metadata="$metadata" \
-e guestinfo.metadata.encoding="base64"
userdata=$(base64 -w0 <<< "$userdata")
govc vm.change -vm "$VM_NAME" \
-e guestinfo.userdata="$userdata" \
```

```
-e guestinfo.userdata.encoding="base64"
```

## Comparing packages installed on Amazon Linux 2023 standard AMI with the AL2023 KVM Image

A comparison of the RPMs present on the AL2023 standard AMI compared with the RPMs present on the AL2023 KVM image.

Package	AMI	KVM
acl	2.3.1	2.3.1
acpid	2.0.32	
alternatives	1.15	1.15
amazon-chrony-config	4.3	
<a href="#">amazon-ec2-net-utils</a>	2.4.1	
<a href="#">amazon-linux-onprem</a>		1.2
amazon-linux-repo-cdn		2023.4.20240513
amazon-linux-repo-s3	2023.4.20240513	
<a href="#">amazon-linux-sb-keys</a>	2023.1	2023.1
<a href="#">amazon-onprem-network</a>		1.2
amazon-rpm-config	228	228
amazon-ssm-agent	3.3.380.0	3.3.380.0
at	3.1.23	3.1.23
attr	2.5.1	2.5.1

Package	AMI	KVM
audit	3.0.6	3.0.6
audit-libs	3.0.6	3.0.6
aws-cfn-bootstrap	2.0	
awscli-2	2.15.30	2.15.30
basesystem	11	11
bash	5.2.15	5.2.15
bash-completion	2.11	2.11
bc	1.07.1	1.07.1
bind-libs	9.16.48	9.16.48
bind-license	9.16.48	9.16.48
bind-utils	9.16.48	9.16.48
<a href="#"><u>binutils</u></a>	2.39	2.39
boost-filesystem	1.75.0	1.75.0
boost-system	1.75.0	1.75.0
boost-thread	1.75.0	1.75.0
bzip2	1.0.8	1.0.8
bzip2-libs	1.0.8	1.0.8
ca-certificates	2023.2.64	2023.2.64
c-ares	1.19.0	
checkpolicy	3.4	3.4

Package	AMI	KVM
chkconfig	1.15	1.15
chrony	4.3	4.3
cloud-init	22.2.2	22.2.2
cloud-init-cfg-ec2	22.2.2	
cloud-init-cfg-onprem		22.2.2
cloud-utils-growpart	0.31	0.31
coreutils	8.32	8.32
coreutils-common	8.32	8.32
cpio	2.13	2.13
cracklib	2.9.6	2.9.6
cracklib-dicts	2.9.6	2.9.6
crontabs	1.11	1.11
crypto-policies	20220428	20220428
crypto-policies-scripts	20220428	20220428
cryptsetup	2.6.1	2.6.1
cryptsetup-libs	2.6.1	2.6.1
<u>curl-minimal</u>	8.5.0	8.5.0
cyrus-sasl-lib	2.1.27	2.1.27
cyrus-sasl-plain	2.1.27	2.1.27

Package	AMI	KVM
dbus	1.12.28	1.12.28
dbus-broker	32	32
dbus-common	1.12.28	1.12.28
dbus-libs	1.12.28	1.12.28
device-mapper	1.02.185	1.02.185
device-mapper-libs	1.02.185	1.02.185
diffutils	3.8	3.8
dnf	4.14.0	4.14.0
dnf-data	4.14.0	4.14.0
dnf-plugin-release-notification	1.2	1.2
dnf-plugins-core	4.3.0	4.3.0
dnf-plugin-support-info	1.2	1.2
dnf-utils	4.3.0	4.3.0
dosfstools	4.2	4.2
dracut	055	055
dracut-config-ec2	3.0	
dracut-config-generic	055	055
dwz	0.14	0.14

Package	AMI	KVM
dyninst	10.2.1	10.2.1
e2fsprogs	1.46.5	1.46.5
e2fsprogs-libs	1.46.5	1.46.5
ec2-hibernate-agent	1.0.8	
ec2-instance-connect	1.1	
ec2-instance-connect-selinux	1.1	
ec2-utils	2.2.0	
ed	1.14.2	1.14.2
efi-filesystem	5	5
efi-srpm-macros	5	5
efivar	38	38
efivar-libs	38	38
elfutils-debuginfod-client	0.188	0.188
elfutils-default-ymama-scope	0.188	0.188
elfutils-libelf	0.188	0.188
elfutils-libs	0.188	0.188
ethtool	5.15	5.15
expat	2.5.0	2.5.0

Package	AMI	KVM
file	5.39	5.39
file-libs	5.39	5.39
filesystem	3.14	3.14
findutils	4.8.0	4.8.0
fonts-srpm-macros	2.0.5	2.0.5
fstrm	0.6.1	0.6.1
fuse-libs	2.9.9	2.9.9
gawk	5.1.0	5.1.0
gdbm-libs	1.19	1.19
gdisk	1.0.8	1.0.8
gettext	0.21	0.21
gettext-libs	0.21	0.21
ghc-srpm-macros	1.5.0	1.5.0
glib2	2.74.7	2.74.7
glibc	2.34	2.34
glibc-all-langpacks	2.34	2.34
glibc-common	2.34	2.34
glibc-gconv-extra	2.34	2.34
glibc-locale-source	2.34	2.34
gmp	6.2.1	6.2.1

Package	AMI	KVM
<a href="#"><u>gnupg2-minimal</u></a>	2.3.7	2.3.7
gnutls	3.8.0	3.8.0
go-srpm-macros	3.2.0	3.2.0
gpgme	1.15.1	1.15.1
gpm-libs	1.20.7	1.20.7
grep	3.8	3.8
groff-base	1.22.4	1.22.4
grub2-common	2.06	2.06
grub2-efi-aa64-ec2	2.06 (aarch64)	2.06 (aarch64)
grub2-efi-x64-ec2	2.06 (x86_64)	2.06 (x86_64)
grub2-pc		2.06 (x86_64)
grub2-pc-modules	2.06	2.06 (noarch)
grub2-tools	2.06	2.06
grub2-tools-minimal	2.06	2.06
grubby	8.40	8.40
gssproxy	0.8.4	0.8.4
gzip	1.12	1.12
hostname	3.23	3.23
hunspell	1.7.0	1.7.0
hunspell-en	0.20140811.1	0.20140811.1

Package	AMI	KVM
hunspell-en-GB	0.20140811.1	0.20140811.1
hunspell-en-US	0.20140811.1	0.20140811.1
hunspell-filesystem	1.7.0	1.7.0
hwdata	0.353	0.353
info	6.7	6.7
inih	49	49
initscripts	10.09	10.09
iproute	5.10.0	5.10.0
iputils	20210202	20210202
irqbalance	1.9.0	1.9.0
jansson	2.14	2.14
jitterentropy	3.4.1	3.4.1
jq	1.7.1	
json-c	0.14	0.14
kbd	2.4.0	2.4.0
kbd-misc	2.4.0	2.4.0
kernel	6.1.90	6.1.90
kernel-livepatch-r epo-cdn		2023.4.20240513
kernel-livepatch-r epo-s3	2023.4.20240513	

Package	AMI	KVM
kernel-modules-extra		6.1.90
kernel-modules-ext ra-common		6.1.90
kernel-srpm-macros	1.0	1.0
kernel-tools	6.1.90	6.1.90
keyutils	1.6.3	1.6.3
keyutils-libs	1.6.3	1.6.3
kmod	29	29
kmod-libs	29	29
kpatch-runtime	0.9.7	0.9.7
krb5-libs	1.21	1.21
less	608	608
libacl	2.3.1	2.3.1
libaio	0.3.111	0.3.111
libarchive	3.5.3	3.5.3
libargon2	20171227	20171227
libassuan	2.5.5	2.5.5
libattr	2.5.1	2.5.1
libbasicobjects	0.1.1	0.1.1
libblkid	2.37.4	2.37.4
libcap	2.48	2.48

Package	AMI	KVM
libcap-ng	0.8.2	0.8.2
libcbor	0.7.0	0.7.0
libcollection	0.7.0	0.7.0
libcom_err	1.46.5	1.46.5
libcomps	0.1.20	0.1.20
libconfig	1.7.2	1.7.2
<a href="#"><u>libcurl-minimal</u></a>	8.5.0	8.5.0
<a href="#"><u>libdb</u></a>	5.3.28	5.3.28
libdhash	0.5.0	
libdnf	0.69.0	0.69.0
libeconf	0.4.0	0.4.0
libedit	3.1	3.1
libev	4.33	4.33
libevent	2.1.12	2.1.12
libfdisk	2.37.4	2.37.4
libffi	3.4.4	3.4.4
libfido2	1.10.0	1.10.0
libgcc	11.4.1	11.4.1
libgcrypt	1.10.2	1.10.2
libgomp	11.4.1	11.4.1

Package	AMI	KVM
libgpg-error	1.42	1.42
libibverbs	48.0	48.0
libidn2	2.3.2	2.3.2
libini_config	1.3.1	1.3.1
libkapi	1.4.0	1.4.0
libkapi-hmaccalc	1.4.0	1.4.0
libldb	2.6.2	
libmaxminddb	1.5.2	1.5.2
libmetalink	0.1.3	0.1.3
libmnl	1.0.4	1.0.4
libmodulemd	2.13.0	2.13.0
libmount	2.37.4	2.37.4
libnfsidmap	2.5.4	2.5.4
libnghttp2	1.59.0	1.59.0
libnl3	3.5.0	3.5.0
libpath_utils	0.2.1	0.2.1
libpcap	1.10.1	1.10.1
libpipeline	1.5.3	1.5.3
libpkgconf	1.8.0	1.8.0
libpsl	0.21.1	0.21.1

Package	AMI	KVM
libpwquality	1.4.4	1.4.4
libref_array	0.1.5	0.1.5
librepo	1.14.5	1.14.5
libreport-filesystem	2.15.2	2.15.2
libseccomp	2.5.3	2.5.3
libselinux	3.4	3.4
libselinux-utils	3.4	3.4
libsemanage	3.4	3.4
libsepolicy	3.4	3.4
libsigsegv	2.13	2.13
libsmartcols	2.37.4	2.37.4
libsolv	0.7.22	0.7.22
libss	1.46.5	1.46.5
libsss_certmap	2.9.4	
libsss_idmap	2.9.4	2.9.4
libsss_nss_idmap	2.9.4	2.9.4
libsss_sudo	2.9.4	
libstdc++	11.4.1	11.4.1
libstoragemgmt	1.9.4	1.9.4
libtalloc	2.3.4	

Package	AMI	KVM
libtasn1	4.19.0	4.19.0
libtdb	1.4.7	
libtevent	0.13.0	
libtextstyle	0.21	0.21
libtirpc	1.3.3	1.3.3
libunistring	0.9.10	0.9.10
libuser	0.63	0.63
libutempter	1.2.1	1.2.1
libuuid	2.37.4	2.37.4
libuv	1.47.0	1.47.0
libverto	0.3.2	0.3.2
libverto-libev	0.3.2	0.3.2
libxcrypt	4.4.33	4.4.33
libxml2	2.10.4	2.10.4
libyaml	0.2.5	0.2.5
libzstd	1.5.5	1.5.5
lm_sensors-libs	3.6.0	3.6.0
lmdb-libs	0.9.29	0.9.29
logrotate	3.20.1	3.20.1
lsof	4.94.0	4.94.0

Package	AMI	KVM
lua-libs	5.4.4	5.4.4
lua-srpm-macros	1	1
lz4-libs	1.9.4	1.9.4
man-db	2.9.3	2.9.3
man-pages	5.10	5.10
microcode_ctl	2.1 (x86_64)	2.1 (x86_64)
mpfr	4.1.0	4.1.0
nano	5.8	5.8
ncurses	6.2	6.2
ncurses-base	6.2	6.2
ncurses-libs	6.2	6.2
nettle	3.8	3.8
net-tools	2.0	2.0
newt	0.52.21	0.52.21
nfs-utils	2.5.4	2.5.4
npth	1.6	1.6
nspr	4.35.0	4.35.0
nss	3.90.0	3.90.0
nss-softokn	3.90.0	3.90.0
nss-softokn-freebl	3.90.0	3.90.0

Package	AMI	KVM
nss-sysinit	3.90.0	3.90.0
nss-util	3.90.0	3.90.0
ntsysv	1.15	1.15
numactl-libs	2.0.14	2.0.14
ocaml-srpm-macros	6	6
oniguruma	6.9.7.1	
openblas-srpm-macros	2	2
openldap	2.4.57	2.4.57
openssh	8.7p1	8.7p1
openssh-clients	8.7p1	8.7p1
openssh-server	8.7p1	8.7p1
openssl	3.0.8	3.0.8
openssl-libs	3.0.8	3.0.8
openssl-pkcs11	0.4.12	0.4.12
os-prober	1.77	1.77
p11-kit	0.24.1	0.24.1
p11-kit-trust	0.24.1	0.24.1
package-notes-srpm-macros	0.4	0.4
pam	1.5.1	1.5.1
parted	3.4	3.4

Package	AMI	KVM
passwd	0.80	0.80
pciutils	3.7.0	3.7.0
pciutils-libs	3.7.0	3.7.0
pcre2	10.40	10.40
pcre2-syntax	10.40	10.40
perl-Carp	1.50	1.50
perl-Class-Struct	0.66	0.66
perl-constant	1.33	1.33
perl-DynaLoader	1.47	1.47
perl-Encode	3.15	3.15
perl-Errno	1.30	1.30
perl-Exporter	5.74	5.74
perl-Fcntl	1.13	1.13
perl-File-Basename	2.85	2.85
perl-File-Path	2.18	2.18
perl-File-stat	1.09	1.09
perl-File-Temp	0.231.100	0.231.100
perl-Getopt-Long	2.52	2.52
perl-Getopt-Std	1.12	1.12
perl-HTTP-Tiny	0.078	0.078

Package	AMI	KVM
perl-if	0.60.800	0.60.800
perl-interpreter	5.32.1	5.32.1
perl-IO	1.43	1.43
perl-IPC-Open3	1.21	1.21
perl-libs	5.32.1	5.32.1
perl-MIME-Base64	3.16	3.16
perl-mro	1.23	1.23
perl-overload	1.31	1.31
perl-overloading	0.02	0.02
perl-parent	0.238	0.238
perl-PathTools	3.78	3.78
perl-Pod-Escapes	1.07	1.07
perl-podlators	4.14	4.14
perl-Pod-Perldoc	3.28.01	3.28.01
perl-Pod-Simple	3.42	3.42
perl-Pod-Usage	2.01	2.01
perl-POSIX	1.94	1.94
perl-Scalar-List-Utils	1.56	1.56
perl-SelectSaver	1.02	1.02
perl-Socket	2.032	2.032

Package	AMI	KVM
perl-srpm-macros	1	1
perl-Storable	3.21	3.21
perl-subs	1.03	1.03
perl-Symbol	1.08	1.08
perl-Term-ANSIColor	5.01	5.01
perl-Term-Cap	1.17	1.17
perl-Text-ParseWords	3.30	3.30
perl-Text-Tabs+Wrap	2021.0726	2021.0726
perl-Time-Local	1.300	1.300
perl-vars	1.05	1.05
pkgconf	1.8.0	1.8.0
pkgconf-m4	1.8.0	1.8.0
pkgconf-pkg-config	1.8.0	1.8.0
policycoreutils	3.4	3.4
policycoreutils-python-utils	3.4	
popt	1.18	1.18
procps-ng	3.3.17	3.3.17
protobuf-c	1.4.1	1.4.1
psacct	6.6.4	6.6.4
psmisc	23.4	23.4

Package	AMI	KVM
publicsuffix-list-dafsa	20240212	20240212
python3	3.9.16	3.9.16
python3-attrs	20.3.0	20.3.0
python3-audit	3.0.6	3.0.6
python3-awscrt	0.19.19	0.19.19
python3-babel	2.9.1	2.9.1
python3-cffi	1.14.5	1.14.5
python3-chardet	4.0.0	4.0.0
python3-colorama	0.4.4	0.4.4
python3-configobj	5.0.6	5.0.6
python3-cryptography	36.0.1	36.0.1
python3-daemon	2.3.0	
python3-dateutil	2.8.1	2.8.1
python3-dbus	1.2.18	1.2.18
python3-distro	1.5.0	1.5.0
python3-dnf	4.14.0	4.14.0
python3-dnf-plugins-core	4.3.0	4.3.0
python3-docutils	0.16	0.16
python3-gpg	1.15.1	1.15.1

Package	AMI	KVM
python3-hawkey	0.69.0	0.69.0
python3-idna	2.10	2.10
python3-jinja2	2.11.3	2.11.3
python3-jmespath	0.10.0	0.10.0
python3-jsonpatch	1.21	1.21
python3-jsonpointer	2.0	2.0
python3-jsonschema	3.2.0	3.2.0
python3-libcomps	0.1.20	0.1.20
python3-libdnf	0.69.0	0.69.0
python3-libs	3.9.16	3.9.16
python3-libselinux	3.4	3.4
python3-libsemanage	3.4	3.4
python3-libstorage mgmt	1.9.4	1.9.4
python3-lockfile	0.12.2	
python3-markupsafe	1.1.1	1.1.1
python3-netifaces	0.10.6	0.10.6
python3-oauthlib	3.0.2	3.0.2
python3-pip-wheel	21.3.1	21.3.1
python3-ply	3.11	3.11

Package	AMI	KVM
python3-policycoreutils	3.4	3.4
python3-prettytable	0.7.2	0.7.2
python3-prompt-toolkit	3.0.24	3.0.24
python3-pycparser	2.20	2.20
python3-persistent	0.17.3	0.17.3
python3-pyserial	3.4	3.4
python3-pysocks	1.7.1	1.7.1
python3-pytz	2022.7.1	2022.7.1
python3-pyyaml	5.4.1	5.4.1
python3-requests	2.25.1	2.25.1
python3-rpm	4.16.1.3	4.16.1.3
python3-ruamel-yaml	0.16.6	0.16.6
python3-ruamel-yaml-clib	0.1.2	0.1.2
python3-setools	4.4.1	4.4.1
python3-setuptools	59.6.0	59.6.0
python3-setuptools-wheel	59.6.0	59.6.0
python3-six	1.15.0	1.15.0
python3-systemd	235	235

Package	AMI	KVM
python3-urllib3	1.25.10	1.25.10
python3-wcwidth	0.2.5	0.2.5
python-chevron	0.13.1	
python-srpm-macros	3.9	3.9
quota	4.06	4.06
quota-nls	4.06	4.06
readline	8.1	8.1
rng-tools	6.14	6.14
rootfiles	8.1	8.1
rpcbind	1.2.6	1.2.6
rpm	4.16.1.3	4.16.1.3
rpm-build-libs	4.16.1.3	4.16.1.3
rpm-libs	4.16.1.3	4.16.1.3
rpm-plugin-selinux	4.16.1.3	4.16.1.3
rpm-plugin-systemd-inhibit	4.16.1.3	4.16.1.3
rpm-sign-libs	4.16.1.3	4.16.1.3
rsync	3.2.6	3.2.6
rust-srpm-macros	21	21
sbsign tools	0.9.4	0.9.4
screen	4.8.0	4.8.0

Package	AMI	KVM
sed	4.8	4.8
selinux-policy	37.22	37.22
selinux-policy-targeted	37.22	37.22
setup	2.13.7	2.13.7
shadow-utils	4.9	4.9
slang	2.3.2	2.3.2
sqlite-libs	3.40.0	3.40.0
sssd-client	2.9.4	2.9.4
sssd-common	2.9.4	
sssd-kcm	2.9.4	
sssd-nfs-idmap	2.9.4	
strace	6.8	6.8
sudo	1.9.15	1.9.15
sysctl-defaults	1.0	1.0
sysstat	12.5.6	12.5.6
systemd	252.16	252.16
systemd-libs	252.16	252.16
systemd-networkd	252.16	252.16
systemd-pam	252.16	252.16
systemd-resolved	252.16	252.16

Package	AMI	KVM
systemd-udev	252.16	252.16
system-release	2023.4.20240513	2023.4.20240513
systemtap-runtime	4.8	4.8
tar	1.34	1.34
tbb	2020.3	2020.3
tcpdump	4.99.1	4.99.1
tcsh	6.24.07	6.24.07
time	1.9	1.9
traceroute	2.1.3	2.1.3
tzdata	2024a	2024a
unzip	6.0	6.0
update-motd	2.2	2.2
userspace-rcu	0.12.1	0.12.1
util-linux	2.37.4	2.37.4
util-linux-core	2.37.4	2.37.4
vim-common	9.0.2153	9.0.2153
vim-data	9.0.2153	9.0.2153
vim-enhanced	9.0.2153	9.0.2153
vim-filesystem	9.0.2153	9.0.2153
vim-minimal	9.0.2153	9.0.2153

Package	AMI	KVM
wget	1.21.3	1.21.3
which	2.21	2.21
words	3.0	3.0
xfsdump	3.1.11	3.1.11
xfsprogs	5.18.0	5.18.0
xxd	9.0.2153	9.0.2153
xxhash-libs	0.8.0	0.8.0
xz	5.2.5	5.2.5
xz-libs	5.2.5	5.2.5
yum	4.14.0	4.14.0
zip	3.0	3.0
zlib	1.2.11	1.2.11
zram-generator	1.1.2	
zram-generator-defaults	1.1.2	
zstd	1.5.5	1.5.5

## Comparing packages installed on Amazon Linux 2023 standard AMI with the AL2023 VMware OVA Image

A comparison of the RPMs present on the AL2023 standard AMI compared with the RPMs present on the AL2023 VMware OVA image.

<b>Package</b>	<b>AMI</b>	<b>VMware OVA</b>
acl	2.3.1	2.3.1
acpid	2.0.32	
alternatives	1.15	1.15
amazon-chrony-config	4.3	
<a href="#"><u>amazon-ec2-net-utils</u></a>	2.4.1	
<a href="#"><u>amazon-linux-onprem</u></a>		1.2
amazon-linux-repo-cdn		2023.4.20240513
amazon-linux-repo-s3	2023.4.20240513	
<a href="#"><u>amazon-linux-sb-keys</u></a>	2023.1	2023.1
<a href="#"><u>amazon-onprem-network</u></a>		1.2
amazon-rpm-config	228	228
amazon-ssm-agent	3.3.380.0	3.3.380.0
at	3.1.23	3.1.23
attr	2.5.1	2.5.1
audit	3.0.6	3.0.6
audit-libs	3.0.6	3.0.6
aws-cfn-bootstrap	2.0	
awscli-2	2.15.30	2.15.30
basesystem	11	11

Package	AMI	VMware OVA
bash	5.2.15	5.2.15
bash-completion	2.11	2.11
bc	1.07.1	1.07.1
bind-libs	9.16.48	9.16.48
bind-license	9.16.48	9.16.48
bind-utils	9.16.48	9.16.48
<a href="#"><u>binutils</u></a>	2.39	2.39
boost-filesystem	1.75.0	1.75.0
boost-system	1.75.0	1.75.0
boost-thread	1.75.0	1.75.0
bzip2	1.0.8	1.0.8
bzip2-libs	1.0.8	1.0.8
ca-certificates	2023.2.64	2023.2.64
c-ares	1.19.0	
checkpolicy	3.4	3.4
chkconfig	1.15	1.15
chrony	4.3	4.3
cloud-init	22.2.2	22.2.2
cloud-init-cfg-ec2	22.2.2	
cloud-init-cfg-onp rem		22.2.2

Package	AMI	VMware OVA
cloud-utils-growpart	0.31	0.31
coreutils	8.32	8.32
coreutils-common	8.32	8.32
cpio	2.13	2.13
cracklib	2.9.6	2.9.6
cracklib-dicts	2.9.6	2.9.6
crontabs	1.11	1.11
crypto-policies	20220428	20220428
crypto-policies-scripts	20220428	20220428
cryptsetup	2.6.1	2.6.1
cryptsetup-libs	2.6.1	2.6.1
<u>curl-minimal</u>	8.5.0	8.5.0
cyrus-sasl-lib	2.1.27	2.1.27
cyrus-sasl-plain	2.1.27	2.1.27
dbus	1.12.28	1.12.28
dbus-broker	32	32
dbus-common	1.12.28	1.12.28
dbus-libs	1.12.28	1.12.28
device-mapper	1.02.185	1.02.185
device-mapper-libs	1.02.185	1.02.185

<b>Package</b>	<b>AMI</b>	<b>VMware OVA</b>
diffutils	3.8	3.8
dnf	4.14.0	4.14.0
dnf-data	4.14.0	4.14.0
dnf-plugin-release-notification	1.2	1.2
dnf-plugins-core	4.3.0	4.3.0
dnf-plugin-support-info	1.2	1.2
dnf-utils	4.3.0	4.3.0
dosfstools	4.2	4.2
dracut	055	055
dracut-config-ec2	3.0	
dracut-config-generic	055	055
dwz	0.14	0.14
dyninst	10.2.1	10.2.1
e2fsprogs	1.46.5	1.46.5
e2fsprogs-libs	1.46.5	1.46.5
ec2-hibinit-agent	1.0.8	
ec2-instance-connect	1.1	
ec2-instance-connect-selinux	1.1	

<b>Package</b>	<b>AMI</b>	<b>VMware OVA</b>
ec2-utils	2.2.0	
ed	1.14.2	1.14.2
efi-filesystem	5	5
efi-srpm-macros	5	5
efivar	38	38
efivar-libs	38	38
elfutils-debuginfod-client	0.188	0.188
elfutils-default-yma-scope	0.188	0.188
elfutils-libelf	0.188	0.188
elfutils-libs	0.188	0.188
ethtool	5.15	5.15
expat	2.5.0	2.5.0
file	5.39	5.39
file-libs	5.39	5.39
filesystem	3.14	3.14
findutils	4.8.0	4.8.0
fonts-srpm-macros	2.0.5	2.0.5
fstrm	0.6.1	0.6.1
fuse3		3.10.4

Package	AMI	VMware OVA
fuse3-libs		3.10.4
fuse-common		3.10.4
fuse-libs	2.9.9	2.9.9
gawk	5.1.0	5.1.0
gdbm-libs	1.19	1.19
gdisk	1.0.8	1.0.8
gettext	0.21	0.21
gettext-libs	0.21	0.21
ghc-srpm-macros	1.5.0	1.5.0
glib2	2.74.7	2.74.7
glibc	2.34	2.34
glibc-all-langpacks	2.34	2.34
glibc-common	2.34	2.34
glibc-gconv-extra	2.34	2.34
glibc-locale-source	2.34	2.34
gmp	6.2.1	6.2.1
<u>gnupg2-minimal</u>	2.3.7	2.3.7
gnutls	3.8.0	3.8.0
go-srpm-macros	3.2.0	3.2.0
gpgme	1.15.1	1.15.1

Package	AMI	VMware OVA
gpm-libs	1.20.7	1.20.7
grep	3.8	3.8
groff-base	1.22.4	1.22.4
grub2-common	2.06	2.06
grub2-efi-x64-ec2	2.06	2.06
grub2-pc		2.06
grub2-pc-modules	2.06	2.06
grub2-tools	2.06	2.06
grub2-tools-minimal	2.06	2.06
grubby	8.40	8.40
gssproxy	0.8.4	0.8.4
gzip	1.12	1.12
hostname	3.23	3.23
hunspell	1.7.0	1.7.0
hunspell-en	0.20140811.1	0.20140811.1
hunspell-en-GB	0.20140811.1	0.20140811.1
hunspell-en-US	0.20140811.1	0.20140811.1
hunspell-filesystem	1.7.0	1.7.0
hwdata	0.353	0.353
info	6.7	6.7

Package	AMI	VMware OVA
inith	49	49
initscripts	10.09	10.09
iproute	5.10.0	5.10.0
iputils	20210202	20210202
irqbalance	1.9.0	1.9.0
jansson	2.14	2.14
jitterentropy	3.4.1	3.4.1
jq	1.7.1	
json-c	0.14	0.14
kbd	2.4.0	2.4.0
kbd-misc	2.4.0	2.4.0
kernel	6.1.90	6.1.90
kernel-livepatch-repo-cdn		2023.4.20240513
kernel-livepatch-repo-s3	2023.4.20240513	
kernel-modules-extra		6.1.90
kernel-modules-ext-ra-common		6.1.90
kernel-srpm-macros	1.0	1.0
kernel-tools	6.1.90	6.1.90

Package	AMI	VMware OVA
keyutils	1.6.3	1.6.3
keyutils-libs	1.6.3	1.6.3
kmod	29	29
kmod-libs	29	29
kpatch-runtime	0.9.7	0.9.7
krb5-libs	1.21	1.21
less	608	608
libacl	2.3.1	2.3.1
libaio	0.3.111	0.3.111
libarchive	3.5.3	3.5.3
libargon2	20171227	20171227
libassuan	2.5.5	2.5.5
libattr	2.5.1	2.5.1
libbasicobjects	0.1.1	0.1.1
libblkid	2.37.4	2.37.4
libcap	2.48	2.48
libcap-ng	0.8.2	0.8.2
libcbor	0.7.0	0.7.0
libcollection	0.7.0	0.7.0
libcom_err	1.46.5	1.46.5

Package	AMI	VMware OVA
libcomps	0.1.20	0.1.20
libconfig	1.7.2	1.7.2
<u>libcurl-minimal</u>	8.5.0	8.5.0
<u>libdb</u>	5.3.28	5.3.28
libdhash	0.5.0	
libdnf	0.69.0	0.69.0
libeconf	0.4.0	0.4.0
libedit	3.1	3.1
libev	4.33	4.33
libevent	2.1.12	2.1.12
libfdisk	2.37.4	2.37.4
libffi	3.4.4	3.4.4
libfido2	1.10.0	1.10.0
libgcc	11.4.1	11.4.1
libgcrypt	1.10.2	1.10.2
libgomp	11.4.1	11.4.1
libgpg-error	1.42	1.42
libibverbs	48.0	48.0
libidn2	2.3.2	2.3.2
libini_config	1.3.1	1.3.1

<b>Package</b>	<b>AMI</b>	<b>VMware OVA</b>
libkapi	1.4.0	1.4.0
libkapi-hmaccalc	1.4.0	1.4.0
libldb	2.6.2	
libmaxminddb	1.5.2	1.5.2
libmetalink	0.1.3	0.1.3
libmnl	1.0.4	1.0.4
libmodulemd	2.13.0	2.13.0
libmount	2.37.4	2.37.4
libmspack		0.10.1
libnfsidmap	2.5.4	2.5.4
libnghttp2	1.59.0	1.59.0
libnl3	3.5.0	3.5.0
libpath_utils	0.2.1	0.2.1
libpcap	1.10.1	1.10.1
libpipeline	1.5.3	1.5.3
libpkgconf	1.8.0	1.8.0
libpsl	0.21.1	0.21.1
libpwquality	1.4.4	1.4.4
libref_array	0.1.5	0.1.5
librepo	1.14.5	1.14.5

Package	AMI	VMware OVA
libreport-filesystem	2.15.2	2.15.2
libseccomp	2.5.3	2.5.3
libselinux	3.4	3.4
libselinux-utils	3.4	3.4
libsemanage	3.4	3.4
libsepolicy	3.4	3.4
libsigsegv	2.13	2.13
libsmartcols	2.37.4	2.37.4
libsolv	0.7.22	0.7.22
libss	1.46.5	1.46.5
libsss_certmap	2.9.4	
libsss_idmap	2.9.4	2.9.4
libsss_nss_idmap	2.9.4	2.9.4
libsss_sudo	2.9.4	
libstdc++	11.4.1	11.4.1
libstoragemgmt	1.9.4	1.9.4
libtalloc	2.3.4	
libtasn1	4.19.0	4.19.0
libtdb	1.4.7	
libevent	0.13.0	

Package	AMI	VMware OVA
libtextstyle	0.21	0.21
libtirpc	1.3.3	1.3.3
libtool-ltdl		2.4.7
libunistring	0.9.10	0.9.10
libuser	0.63	0.63
libutempter	1.2.1	1.2.1
libuuid	2.37.4	2.37.4
libuv	1.47.0	1.47.0
libverto	0.3.2	0.3.2
libverto-libev	0.3.2	0.3.2
libxcrypt	4.4.33	4.4.33
libxml2	2.10.4	2.10.4
libxslt		1.1.34
libyaml	0.2.5	0.2.5
libzstd	1.5.5	1.5.5
lm_sensors-libs	3.6.0	3.6.0
lmdb-libs	0.9.29	0.9.29
logrotate	3.20.1	3.20.1
lsof	4.94.0	4.94.0
lua-libs	5.4.4	5.4.4

<b>Package</b>	<b>AMI</b>	<b>VMware OVA</b>
lua-srpm-macros	1	1
lz4-libs	1.9.4	1.9.4
man-db	2.9.3	2.9.3
man-pages	5.10	5.10
microcode_ctl	2.1	2.1
mpfr	4.1.0	4.1.0
nano	5.8	5.8
ncurses	6.2	6.2
ncurses-base	6.2	6.2
ncurses-libs	6.2	6.2
nettle	3.8	3.8
net-tools	2.0	2.0
newt	0.52.21	0.52.21
nfs-utils	2.5.4	2.5.4
npth	1.6	1.6
nspr	4.35.0	4.35.0
nss	3.90.0	3.90.0
nss-softokn	3.90.0	3.90.0
nss-softokn-freebl	3.90.0	3.90.0
nss-sysinit	3.90.0	3.90.0

<b>Package</b>	<b>AMI</b>	<b>VMware OVA</b>
nss-util	3.90.0	3.90.0
ntsysv	1.15	1.15
numactl-libs	2.0.14	2.0.14
ocaml-srpm-macros	6	6
oniguruma	6.9.7.1	
openblas-srpm-macros	2	2
openldap	2.4.57	2.4.57
openssh	8.7p1	8.7p1
openssh-clients	8.7p1	8.7p1
openssh-server	8.7p1	8.7p1
openssl	3.0.8	3.0.8
openssl-libs	3.0.8	3.0.8
openssl-pkcs11	0.4.12	0.4.12
open-vm-tools		12.3.0
os-prober	1.77	1.77
p11-kit	0.24.1	0.24.1
p11-kit-trust	0.24.1	0.24.1
package-notes-srpm-macros	0.4	0.4
pam	1.5.1	1.5.1
parted	3.4	3.4

<b>Package</b>	<b>AMI</b>	<b>VMware OVA</b>
passwd	0.80	0.80
pciutils	3.7.0	3.7.0
pciutils-libs	3.7.0	3.7.0
pcre2	10.40	10.40
pcre2-syntax	10.40	10.40
perl-Carp	1.50	1.50
perl-Class-Struct	0.66	0.66
perl-constant	1.33	1.33
perl-DynaLoader	1.47	1.47
perl-Encode	3.15	3.15
perl-Errno	1.30	1.30
perl-Exporter	5.74	5.74
perl-Fcntl	1.13	1.13
perl-File-Basename	2.85	2.85
perl-File-Path	2.18	2.18
perl-File-stat	1.09	1.09
perl-File-Temp	0.231.100	0.231.100
perl-Getopt-Long	2.52	2.52
perl-Getopt-Std	1.12	1.12
perl-HTTP-Tiny	0.078	0.078

<b>Package</b>	<b>AMI</b>	<b>VMware OVA</b>
perl-if	0.60.800	0.60.800
perl-interpreter	5.32.1	5.32.1
perl-IO	1.43	1.43
perl-IPC-Open3	1.21	1.21
perl-libs	5.32.1	5.32.1
perl-MIME-Base64	3.16	3.16
perl-mro	1.23	1.23
perl-overload	1.31	1.31
perl-overloading	0.02	0.02
perl-parent	0.238	0.238
perl-PathTools	3.78	3.78
perl-Pod-Escapes	1.07	1.07
perl-podlators	4.14	4.14
perl-Pod-Perldoc	3.28.01	3.28.01
perl-Pod-Simple	3.42	3.42
perl-Pod-Usage	2.01	2.01
perl-POSIX	1.94	1.94
perl-Scalar-List-Utils	1.56	1.56
perl-SelectSaver	1.02	1.02
perl-Socket	2.032	2.032

Package	AMI	VMware OVA
perl-srpm-macros	1	1
perl-Storable	3.21	3.21
perl-subs	1.03	1.03
perl-Symbol	1.08	1.08
perl-Term-ANSIColor	5.01	5.01
perl-Term-Cap	1.17	1.17
perl-Text-ParseWords	3.30	3.30
perl-Text-Tabs+Wrap	2021.0726	2021.0726
perl-Time-Local	1.300	1.300
perl-vars	1.05	1.05
pkgconf	1.8.0	1.8.0
pkgconf-m4	1.8.0	1.8.0
pkgconf-pkg-config	1.8.0	1.8.0
policycoreutils	3.4	3.4
policycoreutils-python-utils	3.4	
popt	1.18	1.18
procps-ng	3.3.17	3.3.17
protobuf-c	1.4.1	1.4.1
psacct	6.6.4	6.6.4
psmisc	23.4	23.4

<b>Package</b>	<b>AMI</b>	<b>VMware OVA</b>
publicsuffix-list-dafsa	20240212	20240212
python3	3.9.16	3.9.16
python3-attrs	20.3.0	20.3.0
python3-audit	3.0.6	3.0.6
python3-awscrt	0.19.19	0.19.19
python3-babel	2.9.1	2.9.1
python3-cffi	1.14.5	1.14.5
python3-chardet	4.0.0	4.0.0
python3-colorama	0.4.4	0.4.4
python3-configobj	5.0.6	5.0.6
python3-cryptography	36.0.1	36.0.1
python3-daemon	2.3.0	
python3-dateutil	2.8.1	2.8.1
python3-dbus	1.2.18	1.2.18
python3-distro	1.5.0	1.5.0
python3-dnf	4.14.0	4.14.0
python3-dnf-plugins-core	4.3.0	4.3.0
python3-docutils	0.16	0.16
python3-gpg	1.15.1	1.15.1

<b>Package</b>	<b>AMI</b>	<b>VMware OVA</b>
python3-hawkey	0.69.0	0.69.0
python3-idna	2.10	2.10
python3-jinja2	2.11.3	2.11.3
python3-jmespath	0.10.0	0.10.0
python3-jsonpatch	1.21	1.21
python3-jsonpointer	2.0	2.0
python3-jsonschema	3.2.0	3.2.0
python3-libcomps	0.1.20	0.1.20
python3-libdnf	0.69.0	0.69.0
python3-libs	3.9.16	3.9.16
python3-libselinux	3.4	3.4
python3-libsemanage	3.4	3.4
python3-libstorage mgmt	1.9.4	1.9.4
python3-lockfile	0.12.2	
python3-markupsafe	1.1.1	1.1.1
python3-netifaces	0.10.6	0.10.6
python3-oauthlib	3.0.2	3.0.2
python3-pip-wheel	21.3.1	21.3.1
python3-ply	3.11	3.11

<b>Package</b>	<b>AMI</b>	<b>VMware OVA</b>
python3-policycoreutils	3.4	3.4
python3-prettytable	0.7.2	0.7.2
python3-prompt-toolkit	3.0.24	3.0.24
python3-pycparser	2.20	2.20
python3-persistent	0.17.3	0.17.3
python3-pyserial	3.4	3.4
python3-pysocks	1.7.1	1.7.1
python3-pytz	2022.7.1	2022.7.1
python3-pyyaml	5.4.1	5.4.1
python3-requests	2.25.1	2.25.1
python3-rpm	4.16.1.3	4.16.1.3
python3-ruamel-yaml	0.16.6	0.16.6
python3-ruamel-yaml-clib	0.1.2	0.1.2
python3-setools	4.4.1	4.4.1
python3-setuptools	59.6.0	59.6.0
python3-setuptools-wheel	59.6.0	59.6.0
python3-six	1.15.0	1.15.0
python3-systemd	235	235

Package	AMI	VMware OVA
python3-urllib3	1.25.10	1.25.10
python3-wcwidth	0.2.5	0.2.5
python-chevron	0.13.1	
python-srpm-macros	3.9	3.9
quota	4.06	4.06
quota-nls	4.06	4.06
readline	8.1	8.1
rng-tools	6.14	6.14
rootfiles	8.1	8.1
rpcbind	1.2.6	1.2.6
rpm	4.16.1.3	4.16.1.3
rpm-build-libs	4.16.1.3	4.16.1.3
rpm-libs	4.16.1.3	4.16.1.3
rpm-plugin-selinux	4.16.1.3	4.16.1.3
rpm-plugin-systemd-inhibit	4.16.1.3	4.16.1.3
rpm-sign-libs	4.16.1.3	4.16.1.3
rsync	3.2.6	3.2.6
rust-srpm-macros	21	21
sbsign tools	0.9.4	0.9.4
screen	4.8.0	4.8.0

<b>Package</b>	<b>AMI</b>	<b>VMware OVA</b>
sed	4.8	4.8
selinux-policy	37.22	37.22
selinux-policy-targeted	37.22	37.22
setup	2.13.7	2.13.7
shadow-utils	4.9	4.9
slang	2.3.2	2.3.2
sqlite-libs	3.40.0	3.40.0
sssd-client	2.9.4	2.9.4
sssd-common	2.9.4	
sssd-kcm	2.9.4	
sssd-nfs-idmap	2.9.4	
strace	6.8	6.8
sudo	1.9.15	1.9.15
sysctl-defaults	1.0	1.0
sysstat	12.5.6	12.5.6
systemd	252.16	252.16
systemd-libs	252.16	252.16
systemd-networkd	252.16	252.16
systemd-pam	252.16	252.16
systemd-resolved	252.16	252.16

Package	AMI	VMware OVA
systemd-udev	252.16	252.16
system-release	2023.4.20240513	2023.4.20240513
systemtap-runtime	4.8	4.8
tar	1.34	1.34
tbb	2020.3	2020.3
tcpdump	4.99.1	4.99.1
tcsh	6.24.07	6.24.07
time	1.9	1.9
traceroute	2.1.3	2.1.3
tzdata	2024a	2024a
unzip	6.0	6.0
update-motd	2.2	2.2
userspace-rcu	0.12.1	0.12.1
util-linux	2.37.4	2.37.4
util-linux-core	2.37.4	2.37.4
vim-common	9.0.2153	9.0.2153
vim-data	9.0.2153	9.0.2153
vim-enhanced	9.0.2153	9.0.2153
vim-filesystem	9.0.2153	9.0.2153
vim-minimal	9.0.2153	9.0.2153

<b>Package</b>	<b>AMI</b>	<b>VMware OVA</b>
wget	1.21.3	1.21.3
which	2.21	2.21
words	3.0	3.0
xfsdump	3.1.11	3.1.11
xfsprogs	5.18.0	5.18.0
xmlsec1		1.2.33
xmlsec1-openssl		1.2.33
xxd	9.0.2153	9.0.2153
xxhash-libs	0.8.0	0.8.0
xz	5.2.5	5.2.5
xz-libs	5.2.5	5.2.5
yum	4.14.0	4.14.0
zip	3.0	3.0
zlib	1.2.11	1.2.11
zram-generator	1.1.2	
zram-generator-defaults	1.1.2	
zstd	1.5.5	1.5.5

# Comparing packages installed on Amazon Linux 2023 standard AMI with the AL2023 Hyper-V image

A comparison of the RPMs present on the AL2023 standard AMI compared with the RPMs present on the AL2023 Hyper-V image.

Package	AMI	Hyper-V VHDX
acl	2.3.1	2.3.1
acpid	2.0.32	
alternatives	1.15	1.15
amazon-chrony-config	4.3	
<a href="#">amazon-ec2-net-utils</a>	2.4.1	
<a href="#">amazon-linux-onprem</a>		1.2
amazon-linux-repo-cdn		2023.4.20240319
amazon-linux-repo-s3	2023.4.20240319	
<a href="#">amazon-linux-sb-keys</a>	2023.1	2023.1
<a href="#">amazon-onprem-network</a>		1.2
amazon-rpm-config	228	228
amazon-ssm-agent	3.2.2303.0	3.2.2303.0
at	3.1.23	3.1.23
attr	2.5.1	2.5.1
audit	3.0.6	3.0.6

Package	AMI	Hyper-V VHDX
audit-libs	3.0.6	3.0.6
aws-cfn-bootstrap	2.0	
awscli-2	2.14.5	2.14.5
basesystem	11	11
bash	5.2.15	5.2.15
bash-completion	2.11	2.11
bc	1.07.1	1.07.1
bind-libs	9.16.48	9.16.48
bind-license	9.16.48	9.16.48
bind-utils	9.16.48	9.16.48
<u>binutils</u>	2.39	2.39
boost-filesystem	1.75.0	1.75.0
boost-system	1.75.0	1.75.0
boost-thread	1.75.0	1.75.0
bzip2	1.0.8	1.0.8
bzip2-libs	1.0.8	1.0.8
ca-certificates	2023.2.64	2023.2.64
c-ares	1.19.0	
checkpolicy	3.4	3.4
chkconfig	1.15	1.15

Package	AMI	Hyper-V VHDX
chrony	4.3	4.3
cloud-init	22.2.2	22.2.2
cloud-init-cfg-ec2	22.2.2	
cloud-init-cfg-onprem		22.2.2
cloud-utils-growpart	0.31	0.31
coreutils	8.32	8.32
coreutils-common	8.32	8.32
cpio	2.13	2.13
cracklib	2.9.6	2.9.6
cracklib-dicts	2.9.6	2.9.6
crontabs	1.11	1.11
crypto-policies	20220428	20220428
crypto-policies-scripts	20220428	20220428
cryptsetup	2.6.1	2.6.1
cryptsetup-libs	2.6.1	2.6.1
<u>curl-minimal</u>	8.5.0	8.5.0
cyrus-sasl-lib	2.1.27	2.1.27
cyrus-sasl-plain	2.1.27	2.1.27
dbus	1.12.28	1.12.28

Package	AMI	Hyper-V VHDX
dbus-broker	32	32
dbus-common	1.12.28	1.12.28
dbus-libs	1.12.28	1.12.28
device-mapper	1.02.185	1.02.185
device-mapper-libs	1.02.185	1.02.185
diffutils	3.8	3.8
dnf	4.14.0	4.14.0
dnf-data	4.14.0	4.14.0
dnf-plugin-release-notification	1.2	1.2
dnf-plugins-core	4.3.0	4.3.0
dnf-plugin-support-info	1.2	1.2
dnf-utils	4.3.0	4.3.0
dosfstools	4.2	4.2
dracut	055	055
dracut-config-ec2	3.0	
dracut-config-generic	055	055
dwz	0.14	0.14
dyninst	10.2.1	10.2.1

Package	AMI	Hyper-V VHDX
e2fsprogs	1.46.5	1.46.5
e2fsprogs-libs	1.46.5	1.46.5
ec2-hibinit-agent	1.0.8	
ec2-instance-connect	1.1	
ec2-instance-connect-selinux	1.1	
ec2-utils	2.2.0	
ed	1.14.2	1.14.2
efi-filesystem	5	5
efi-srpm-macros	5	5
efivar	38	38
efivar-libs	38	38
elfutils-debuginfod-client	0.188	0.188
elfutils-default-ymama-scope	0.188	0.188
elfutils-libelf	0.188	0.188
elfutils-libs	0.188	0.188
ethtool	5.15	5.15
expat	2.5.0	2.5.0
file	5.39	5.39

Package	AMI	Hyper-V VHDX
file-libs	5.39	5.39
filesystem	3.14	3.14
findutils	4.8.0	4.8.0
fonts-srpm-macros	2.0.5	2.0.5
fstrm	0.6.1	0.6.1
fuse-libs	2.9.9	2.9.9
gawk	5.1.0	5.1.0
gdbm-libs	1.19	1.19
gdisk	1.0.8	1.0.8
gettext	0.21	0.21
gettext-libs	0.21	0.21
ghc-srpm-macros	1.5.0	1.5.0
glib2	2.74.7	2.74.7
glibc	2.34	2.34
glibc-all-langpacks	2.34	2.34
glibc-common	2.34	2.34
glibc-gconv-extra	2.34	2.34
glibc-locale-source	2.34	2.34
gmp	6.2.1	6.2.1
<a href="#"><u>gnupg2-minimal</u></a>	2.3.7	2.3.7

Package	AMI	Hyper-V VHDX
gnutls	3.8.0	3.8.0
go-srpm-macros	3.2.0	3.2.0
gpgme	1.15.1	1.15.1
gpm-libs	1.20.7	1.20.7
grep	3.8	3.8
groff-base	1.22.4	1.22.4
grub2-common	2.06	2.06
grub2-efi-x64-ec2	2.06	2.06
grub2-pc		2.06
grub2-pc-modules	2.06	2.06
grub2-tools	2.06	2.06
grub2-tools-minimal	2.06	2.06
grubby	8.40	8.40
gssproxy	0.8.4	0.8.4
gzip	1.12	1.12
hostname	3.23	3.23
hunspell	1.7.0	1.7.0
hunspell-en	0.20140811.1	0.20140811.1
hunspell-en-GB	0.20140811.1	0.20140811.1
hunspell-en-US	0.20140811.1	0.20140811.1

Package	AMI	Hyper-V VHDX
hunspell-filesystem	1.7.0	1.7.0
hwdata	0.353	0.353
<a href="#"><u>hyperv-daemons</u></a>		0
<a href="#"><u>hyperv-daemons-license</u></a>		0
<a href="#"><u>hypervfcopyd</u></a>		0
<a href="#"><u>hypervkvpd</u></a>		0
<a href="#"><u>hyperv-tools</u></a>		0
hypervvssd		0
info	6.7	6.7
inih	49	49
initscripts	10.09	10.09
iproute	5.10.0	5.10.0
iputils	20210202	20210202
irqbalance	1.9.0	1.9.0
jansson	2.14	2.14
jitterentropy	3.4.1	3.4.1
jq	1.7.1	1.7.1
json-c	0.14	0.14
kbd	2.4.0	2.4.0
kbd-misc	2.4.0	2.4.0

Package	AMI	Hyper-V VHDX
kernel	6.1.79	6.1.79
kernel-livepatch-repo-cdn		2023.4.20240319
kernel-livepatch-repo-s3	2023.4.20240319	
kernel-modules-extra		6.1.79
kernel-modules-extra-common		6.1.79
kernel-srpm-macros	1.0	1.0
kernel-tools	6.1.79	6.1.79
keyutils	1.6.3	1.6.3
keyutils-libs	1.6.3	1.6.3
kmod	29	29
kmod-libs	29	29
kpatch-runtime	0.9.7	0.9.7
krb5-libs	1.21	1.21
less	608	608
libacl	2.3.1	2.3.1
libaio	0.3.111	0.3.111
libarchive	3.5.3	3.5.3
libargon2	20171227	20171227

Package	AMI	Hyper-V VHDX
libassuan	2.5.5	2.5.5
libattr	2.5.1	2.5.1
libbasicobjects	0.1.1	0.1.1
libblkid	2.37.4	2.37.4
libcap	2.48	2.48
libcap-ng	0.8.2	0.8.2
libcbor	0.7.0	0.7.0
libcollection	0.7.0	0.7.0
libcom_err	1.46.5	1.46.5
libcomps	0.1.20	0.1.20
libconfig	1.7.2	1.7.2
<a href="#"><u>libcurl-minimal</u></a>	8.5.0	8.5.0
<a href="#"><u>libdb</u></a>	5.3.28	5.3.28
libdhash	0.5.0	
libdnf	0.69.0	0.69.0
libeconf	0.4.0	0.4.0
libedit	3.1	3.1
libev	4.33	4.33
libevent	2.1.12	2.1.12
libfdisk	2.37.4	2.37.4

Package	AMI	Hyper-V VHDX
libffi	3.4.4	3.4.4
libfido2	1.10.0	1.10.0
libgcc	11.4.1	11.4.1
libgcrypt	1.10.2	1.10.2
libgomp	11.4.1	11.4.1
libgpg-error	1.42	1.42
libibverbs	48.0	48.0
libidn2	2.3.2	2.3.2
libini_config	1.3.1	1.3.1
libkapi	1.4.0	1.4.0
libkapi-hmaccalc	1.4.0	1.4.0
libldb	2.6.2	
libmaxminddb	1.5.2	1.5.2
libmetalink	0.1.3	0.1.3
libmnl	1.0.4	1.0.4
libmodulemd	2.13.0	2.13.0
libmount	2.37.4	2.37.4
libnfsidmap	2.5.4	2.5.4
libnghttp2	1.57.0	1.57.0
libnl3	3.5.0	3.5.0

Package	AMI	Hyper-V VHDX
libpath_utils	0.2.1	0.2.1
libpcap	1.10.1	1.10.1
libpipeline	1.5.3	1.5.3
libpkgconf	1.8.0	1.8.0
libpsl	0.21.1	0.21.1
libpwquality	1.4.4	1.4.4
libref_array	0.1.5	0.1.5
librepo	1.14.5	1.14.5
libreport-filesystem	2.15.2	2.15.2
libseccomp	2.5.3	2.5.3
libselinux	3.4	3.4
libsSelinux-utils	3.4	3.4
libsemanage	3.4	3.4
libsepolicy	3.4	3.4
libsigsegv	2.13	2.13
libsmartcols	2.37.4	2.37.4
libsolv	0.7.22	0.7.22
libss	1.46.5	1.46.5
libsss_certmap	2.9.4	
libsss_idmap	2.9.4	2.9.4

Package	AMI	Hyper-V VHDX
libsss_nss_idmap	2.9.4	2.9.4
libsss_sudo	2.9.4	
libstdc++	11.4.1	11.4.1
libstoragemgmt	1.9.4	1.9.4
libtalloc	2.3.4	
libtasn1	4.19.0	4.19.0
libtdb	1.4.7	
libtevent	0.13.0	
libtextstyle	0.21	0.21
libtirpc	1.3.3	1.3.3
libunistring	0.9.10	0.9.10
libuser	0.63	0.63
libutempter	1.2.1	1.2.1
libuuid	2.37.4	2.37.4
libuv	1.47.0	1.47.0
libverto	0.3.2	0.3.2
libverto-libev	0.3.2	0.3.2
libxcrypt	4.4.33	4.4.33
libxml2	2.10.4	2.10.4
libyaml	0.2.5	0.2.5

Package	AMI	Hyper-V VHDX
libzstd	1.5.5	1.5.5
lm_sensors-libs	3.6.0	3.6.0
lmdb-libs	0.9.29	0.9.29
logrotate	3.20.1	3.20.1
lsof	4.94.0	4.94.0
lua-libs	5.4.4	5.4.4
lua-srpm-macros	1	1
lz4-libs	1.9.4	1.9.4
man-db	2.9.3	2.9.3
man-pages	5.10	5.10
microcode_ctl	2.1	2.1
mpfr	4.1.0	4.1.0
nano	5.8	5.8
ncurses	6.2	6.2
ncurses-base	6.2	6.2
ncurses-libs	6.2	6.2
nettle	3.8	3.8
net-tools	2.0	2.0
newt	0.52.21	0.52.21
nfs-utils	2.5.4	2.5.4

Package	AMI	Hyper-V VHDX
npth	1.6	1.6
nspr	4.35.0	4.35.0
nss	3.90.0	3.90.0
nss-softokn	3.90.0	3.90.0
nss-softokn-freebl	3.90.0	3.90.0
nss-sysinit	3.90.0	3.90.0
nss-util	3.90.0	3.90.0
ntsysv	1.15	1.15
numactl-libs	2.0.14	2.0.14
ocaml-srpm-macros	6	6
oniguruma	6.9.7.1	6.9.7.1
openblas-srpm-macros	2	2
openldap	2.4.57	2.4.57
openssh	8.7p1	8.7p1
openssh-clients	8.7p1	8.7p1
openssh-server	8.7p1	8.7p1
openssl	3.0.8	3.0.8
openssl-libs	3.0.8	3.0.8
openssl-pkcs11	0.4.12	0.4.12
os-prober	1.77	1.77

Package	AMI	Hyper-V VHDX
p11-kit	0.24.1	0.24.1
p11-kit-trust	0.24.1	0.24.1
package-notes-srpm-macros	0.4	0.4
pam	1.5.1	1.5.1
parted	3.4	3.4
passwd	0.80	0.80
pciutils	3.7.0	3.7.0
pciutils-libs	3.7.0	3.7.0
pcre2	10.40	10.40
pcre2-syntax	10.40	10.40
perl-Carp	1.50	1.50
perl-Class-Struct	0.66	0.66
perl-constant	1.33	1.33
perl-DynaLoader	1.47	1.47
perl-Encode	3.15	3.15
perl-Errno	1.30	1.30
perl-Exporter	5.74	5.74
perl-Fcntl	1.13	1.13
perl-File-Basename	2.85	2.85
perl-File-Path	2.18	2.18

Package	AMI	Hyper-V VHDX
perl-File-stat	1.09	1.09
perl-File-Temp	0.231.100	0.231.100
perl-Getopt-Long	2.52	2.52
perl-Getopt-Std	1.12	1.12
perl-HTTP-Tiny	0.078	0.078
perl-if	0.60.800	0.60.800
perl-interpreter	5.32.1	5.32.1
perl-IO	1.43	1.43
perl-IPC-Open3	1.21	1.21
perl-libs	5.32.1	5.32.1
perl-MIME-Base64	3.16	3.16
perl-mro	1.23	1.23
perl-overload	1.31	1.31
perl-overloading	0.02	0.02
perl-parent	0.238	0.238
perl-PathTools	3.78	3.78
perl-Pod-Escapes	1.07	1.07
perl-podlators	4.14	4.14
perl-Pod-Perldoc	3.28.01	3.28.01
perl-Pod-Simple	3.42	3.42

Package	AMI	Hyper-V VHDX
perl-Pod-Usage	2.01	2.01
perl-POSIX	1.94	1.94
perl-Scalar-List-Utilities	1.56	1.56
perl-SelectSaver	1.02	1.02
perl-Socket	2.032	2.032
perl-srpm-macros	1	1
perl-Storable	3.21	3.21
perl-subs	1.03	1.03
perl-Symbol	1.08	1.08
perl-Term-ANSIColor	5.01	5.01
perl-Term-Cap	1.17	1.17
perl-Text-ParseWords	3.30	3.30
perl-Text-Tabs+Wrap	2021.0726	2021.0726
perl-Time-Local	1.300	1.300
perl-vars	1.05	1.05
pkgconf	1.8.0	1.8.0
pkgconf-m4	1.8.0	1.8.0
pkgconf-pkg-config	1.8.0	1.8.0
policycoreutils	3.4	3.4

Package	AMI	Hyper-V VHDX
policycoreutils-py thon-utils	3.4	
popt	1.18	1.18
procps-ng	3.3.17	3.3.17
protobuf-c	1.4.1	1.4.1
psacct	6.6.4	6.6.4
psmisc	23.4	23.4
publicsuffix-list-dafsa	20240212	20240212
python3	3.9.16	3.9.16
python3-attrs	20.3.0	20.3.0
python3-audit	3.0.6	3.0.6
python3-awscrt	0.19.19	0.19.19
python3-babel	2.9.1	2.9.1
python3-cffi	1.14.5	1.14.5
python3-chardet	4.0.0	4.0.0
python3-colorama	0.4.4	0.4.4
python3-configobj	5.0.6	5.0.6
python3-cryptography	36.0.1	36.0.1
python3-daemon	2.3.0	
python3-dateutil	2.8.1	2.8.1

Package	AMI	Hyper-V VHDX
python3-dbus	1.2.18	1.2.18
python3-distro	1.5.0	1.5.0
python3-dnf	4.14.0	4.14.0
python3-dnf-plugins-core	4.3.0	4.3.0
python3-docutils	0.16	0.16
python3-gpg	1.15.1	1.15.1
python3-hawkey	0.69.0	0.69.0
python3-idna	2.10	2.10
python3-jinja2	2.11.3	2.11.3
python3-jmespath	0.10.0	0.10.0
python3-jsonpatch	1.21	1.21
python3-jsonpointer	2.0	2.0
python3-jsonschema	3.2.0	3.2.0
python3-libcomps	0.1.20	0.1.20
python3-libdnf	0.69.0	0.69.0
python3-libs	3.9.16	3.9.16
python3-libselinux	3.4	3.4
python3-libsemanage	3.4	3.4
python3-libstorage	1.9.4	1.9.4
mgmt		

Package	AMI	Hyper-V VHDX
python3-lockfile	0.12.2	
python3-markupsafe	1.1.1	1.1.1
python3-netifaces	0.10.6	0.10.6
python3-oauthlib	3.0.2	3.0.2
python3-pip-wheel	21.3.1	21.3.1
python3-ply	3.11	3.11
python3-policycoreutils	3.4	3.4
python3-prettytable	0.7.2	0.7.2
python3-prompt-toolkit	3.0.24	3.0.24
python3-pycparser	2.20	2.20
python3-pyrsistent	0.17.3	0.17.3
python3-pyserial	3.4	3.4
python3-pysocks	1.7.1	1.7.1
python3-pytz	2022.7.1	2022.7.1
python3-pyyaml	5.4.1	5.4.1
python3-requests	2.25.1	2.25.1
python3-rpm	4.16.1.3	4.16.1.3
python3-ruamel-yaml	0.16.6	0.16.6

Package	AMI	Hyper-V VHDX
python3-ruamel-yaml- clib	0.1.2	0.1.2
python3-setools	4.4.1	4.4.1
python3-setuptools	59.6.0	59.6.0
python3-setuptools- wheel	59.6.0	59.6.0
python3-six	1.15.0	1.15.0
python3-systemd	235	235
python3-urllib3	1.25.10	1.25.10
python3-wcwidth	0.2.5	0.2.5
python-chevron	0.13.1	
python-srpm-macros	3.9	3.9
quota	4.06	4.06
quota-nls	4.06	4.06
readline	8.1	8.1
rng-tools	6.14	6.14
rootfiles	8.1	8.1
rpcbind	1.2.6	1.2.6
rpm	4.16.1.3	4.16.1.3
rpm-build-libs	4.16.1.3	4.16.1.3
rpm-libs	4.16.1.3	4.16.1.3

Package	AMI	Hyper-V VHDX
rpm-plugin-selinux	4.16.1.3	4.16.1.3
rpm-plugin-systemd-inhibit	4.16.1.3	4.16.1.3
rpm-sign-libs	4.16.1.3	4.16.1.3
rsync	3.2.6	3.2.6
rust-srpm-macros	21	21
sbsigntools	0.9.4	0.9.4
screen	4.8.0	4.8.0
sed	4.8	4.8
selinux-policy	37.22	37.22
selinux-policy-targeted	37.22	37.22
setup	2.13.7	2.13.7
shadow-utils	4.9	4.9
slang	2.3.2	2.3.2
sqlite-libs	3.40.0	3.40.0
sssd-client	2.9.4	2.9.4
sssd-common	2.9.4	
sssd-kcm	2.9.4	
sssd-nfs-idmap	2.9.4	
strace	5.16	5.16

Package	AMI	Hyper-V VHDX
sudo	1.9.14	1.9.14
sysctl-defaults	1.0	1.0
sysstat	12.5.6	12.5.6
systemd	252.16	252.16
systemd-libs	252.16	252.16
systemd-networkd	252.16	252.16
systemd-pam	252.16	252.16
systemd-resolved	252.16	252.16
systemd-udev	252.16	252.16
system-release	2023.4.20240319	2023.4.20240319
systemtap-runtime	4.8	4.8
tar	1.34	1.34
tbb	2020.3	2020.3
tcpdump	4.99.1	4.99.1
tcsh	6.24.07	6.24.07
time	1.9	1.9
traceroute	2.1.3	2.1.3
tzdata	2024a	2024a
unzip	6.0	6.0
update-motd	2.2	2.2

Package	AMI	Hyper-V VHDX
userspace-rcu	0.12.1	0.12.1
util-linux	2.37.4	2.37.4
util-linux-core	2.37.4	2.37.4
vim-common	9.0.2153	9.0.2153
vim-data	9.0.2153	9.0.2153
vim-enhanced	9.0.2153	9.0.2153
vim-filesystem	9.0.2153	9.0.2153
vim-minimal	9.0.2153	9.0.2153
wget	1.21.3	1.21.3
which	2.21	2.21
words	3.0	3.0
xfsdump	3.1.11	3.1.11
xfsprogs	5.18.0	5.18.0
xxd	9.0.2153	9.0.2153
xxhash-libs	0.8.0	0.8.0
xz	5.2.5	5.2.5
xz-libs	5.2.5	5.2.5
yum	4.14.0	4.14.0
zip	3.0	3.0
zlib	1.2.11	1.2.11

Package	AMI	Hyper-V VHDX
zram-generator	1.1.2	
zram-generator-defaulsts	1.1.2	
zstd	1.5.5	1.5.5

# Updating AL2023

It's important to keep up to date with AL2023 releases so that you can benefit from security updates and new features. With AL2023, you can ensure consistency between package versions and updates across your environment through [Using Deterministic upgrades through versioned repository on AL2023](#).

## Topics

- [Receive notifications on new updates](#)
- [Manage package and operating system updates in AL2023](#)
- [Using Deterministic upgrades through versioned repository on AL2023](#)
- [Kernel Live Patching on AL2023](#)

## Receive notifications on new updates

You can receive notifications whenever a new AL2023 AMI is released. Notifications are published with [Amazon SNS](#) using the following topic.

```
arn:aws:sns:us-east-1:137112412989:amazon-linux-2023-ami-updates
```

Messages are posted here when a new AL2023 AMI is published. The version of the AMI will be included in the message.

These messages can be received using several different methods. We recommend that you use the following method.

1. Open the [Amazon SNS console](#).
2. In the navigation bar, change the AWS Region to **US East (N. Virginia)**, if necessary. You must select the Region where the SNS notification that you're subscribing to was created.
3. In the navigation pane, choose **Subscriptions**, **Create subscription**.
4. For the **Create subscription** dialog box, do the following:
  - a. For **Topic ARN**, copy and paste the following **Amazon Resource Name (ARN)**:  
**arn:aws:sns:us-east-1:137112412989:amazon-linux-2023-ami-updates**.
  - b. For **Protocol**, choose **Email**.

- c. For **Endpoint**, enter an email address that you can use to receive the notifications.
  - d. Choose **Create subscription**.
5. You receive a confirmation email with the subject line "AWS Notification - Subscription Confirmation". Open the email and choose **Confirm subscription** to complete your subscription.

## Manage package and operating system updates in AL2023

Unlike previous versions of Amazon Linux, AL2023 AMIs are locked to a specific version of the Amazon Linux repository. To apply both security and bug fixes to an AL2023 instance, update the DNF configuration. Alternatively, launch a newer AL2023 instance.

This section describes how to manage DNF packages and repositories on a running instance. It also describes how to configure DNF from a user data script to enable the latest available Amazon Linux repository at launch time. For more information, see [DNF Command Reference](#).

### Topics

- [Checking for available package updates](#)
- [Applying security updates using DNF and repository versions](#)
- [Automatic service restart after \(security\) updates](#)
- [Launching an instance with the latest repository version enabled](#)
- [Getting package support information](#)
- [Checking for newer repository versions](#)
- [Adding, enabling, or disabling new repositories](#)
- [Adding repositories with cloud-init](#)

## Checking for available package updates

You can use the `dnf check-update` command to check for any updates for your system. For AL2023, we recommend that you add the `--releasever=version-number` option to the command.

When you add this option, DNF also checks for updates for a later version of the repository. For example, after you run the `dnf check-update` command, use the latest returned version as the value for the `version-number`.

If the instance is updated to use the latest version of the repository, the output includes a list of all the packages to be updated.

 **Note**

If you don't specify the release version with the optional flag to the `dnf check-update` command, only the currently configured repository version is checked. This means that packages in the later version of the repository aren't checked.

```
$ sudo dnf check-update --releasever=2023.0.20230210
Last metadata expiration check: 0:06:13 ago on Mon 13 Feb 2023 10:39:32 PM UTC.

bind-libs.x86_64          32:9.16.27-1.amzn2023      amazonlinux
bind-license.noarch        32:9.16.27-1.amzn2023      amazonlinux
bind-utils.x86_64          32:9.16.27-1.amzn2023      amazonlinux
cloud-init.noarch         22.2.2-1.amzn2023.1.4    amazonlinux
dnf.noarch                4.12.0-2.amzn2023.0.1    amazonlinux
dnf-data.noarch           4.12.0-2.amzn2023.0.1    amazonlinux
dracut.x86_64              055-6.amzn2023.0.4      amazonlinux
dracut-config-generic.x86_64 055-6.amzn2023.0.4      amazonlinux
glib2.x86_64               2.73.2-678.amzn2023      amazonlinux
gmp.x86_64                 1:6.2.1-2.amzn2023      amazonlinux
grep.x86_64                3.8-1.amzn2023.0.1      amazonlinux
kpatch-runtime.noarch       0.9.4-7.amzn2023      amazonlinux
libgcc.x86_64              11.3.1-2.amzn2023.0.6    amazonlinux
libgomp.x86_64             11.3.1-2.amzn2023.0.6    amazonlinux
libpkgconf.x86_64          1.7.3-7.amzn2023.0.1      amazonlinux
libstdc++.x86_64           11.3.1-2.amzn2023.0.6    amazonlinux
lz4-libs.x86_64            1.9.4-1.amzn2023      amazonlinux
pkgconf.x86_64              1.7.3-7.amzn2023.0.1      amazonlinux
pkgconf-m4.noarch          1.7.3-7.amzn2023.0.1      amazonlinux
pkgconf-pkg-config.x86_64   1.7.3-7.amzn2023.0.1      amazonlinux
python3-dnf.noarch         4.12.0-2.amzn2023.0.1      amazonlinux
python3-rpm.x86_64          4.16.1.3-12.amzn2023.0.2  amazonlinux
rpm.x86_64                 4.16.1.3-12.amzn2023.0.2  amazonlinux
rpm-build-libs.x86_64       4.16.1.3-12.amzn2023.0.2  amazonlinux
rpm-libs.x86_64             4.16.1.3-12.amzn2023.0.2  amazonlinux
rpm-plugin-selinux.x86_64   4.16.1.3-12.amzn2023.0.2  amazonlinux
rpm-plugin-systemd-inhibit.x86_64 4.16.1.3-12.amzn2023.0.2  amazonlinux
rpm-sign-libs.x86_64        4.16.1.3-12.amzn2023.0.2  amazonlinux
slang.x86_64                2.3.2-9.amzn2023.0.1      amazonlinux
```

system-release.noarch	2023.0.20230210-0.amzn2023	amazonlinux
systemd.x86_64	250.8-1.amzn2023.0.1	amazonlinux
systemd-libs.x86_64	250.8-1.amzn2023.0.1	amazonlinux
systemd-networkd.x86_64	250.8-1.amzn2023.0.1	amazonlinux
systemd-pam.x86_64	250.8-1.amzn2023.0.1	amazonlinux
systemd-resolved.x86_64	250.8-1.amzn2023.0.1	amazonlinux
systemd-udev.x86_64	250.8-1.amzn2023.0.1	amazonlinux
vim-common.x86_64	2:9.0.327-1.amzn2023.0.1	amazonlinux
vim-data.noarch	2:9.0.327-1.amzn2023.0.1	amazonlinux
vim-enhanced.x86_64	2:9.0.327-1.amzn2023.0.1	amazonlinux
vim-filesystem.noarch	2:9.0.327-1.amzn2023.0.1	amazonlinux
vim-minimal.x86_64	2:9.0.327-1.amzn2023.0.1	amazonlinux
wget.x86_64	1.21.3-1.amzn2023	amazonlinux
yum.noarch	4.12.0-2.amzn2023.0.1	amazonlinux

For this command, if there are newer packages available, the return code is 100. If there aren't any newer packages available, the return code is 0. In addition, the output also lists all the packages to update.

## Applying security updates using DNF and repository versions

New package updates and security updates are made available to new repository versions only. For instances that you launched from earlier AL2023 AMI versions, you must update the repository version before you can install security updates. The `dnf check-release-update` command includes an example update command that updates all the packages that are installed on the system to versions in a newer repository.

```
$ sudo dnf update --releasever=2023.0.20230210
Last metadata expiration check: 0:01:40 ago on Mon 13 Feb 2023 10:39:32 PM UTC.
Dependencies resolved.
=====
Package           Arch   Version            Repository  Size
=====
Upgrading:
bind-libs          x86_64  32:9.16.27-1.amzn2023    amazonlinux 1.2 M
bind-license        noarch  32:9.16.27-1.amzn2023    amazonlinux 16 k
bind-utils          x86_64  32:9.16.27-1.amzn2023    amazonlinux 202 k
cloud-init          noarch  22.2.2-1.amzn2023.1.4    amazonlinux 1.1 M
dnf                noarch  4.12.0-2.amzn2023.0.1    amazonlinux 454 k
dnf-data           noarch  4.12.0-2.amzn2023.0.1    amazonlinux 42 k
dracut             x86_64  055-6.amzn2023.0.4      amazonlinux 345 k
dracut-config-generic x86_64  055-6.amzn2023.0.4      amazonlinux 8.5 k
```

glib2	x86_64 2.73.2-678.amzn2023	amazonlinux 2.7 M
gmp	x86_64 1:6.2.1-2.amzn2023	amazonlinux 324 k
grep	x86_64 3.8-1.amzn2023.0.1	amazonlinux 316 k
kpatch-runtime	noarch 0.9.4-7.amzn2023	amazonlinux 30 k
libgcc	x86_64 11.3.1-2.amzn2023.0.6	amazonlinux 121 k
libgomp	x86_64 11.3.1-2.amzn2023.0.6	amazonlinux 296 k
libpkgconf	x86_64 1.7.3-7.amzn2023.0.1	amazonlinux 37 k
libstdc++	x86_64 11.3.1-2.amzn2023.0.6	amazonlinux 758 k
lz4-libs	x86_64 1.9.4-1.amzn2023	amazonlinux 81 k
pkgconf	x86_64 1.7.3-7.amzn2023.0.1	amazonlinux 41 k
pkgconf-m4	noarch 1.7.3-7.amzn2023.0.1	amazonlinux 15 k
pkgconf-pkg-config	x86_64 1.7.3-7.amzn2023.0.1	amazonlinux 11 k
python3-dnf	noarch 4.12.0-2.amzn2023.0.1	amazonlinux 415 k
python3-rpm	x86_64 4.16.1.3-12.amzn2023.0.2	amazonlinux 89 k
rpm	x86_64 4.16.1.3-12.amzn2023.0.2	amazonlinux 487 k
rpm-build-libs	x86_64 4.16.1.3-12.amzn2023.0.2	amazonlinux 92 k
rpm-libs	x86_64 4.16.1.3-12.amzn2023.0.2	amazonlinux 311 k
rpm-plugin-selinux	x86_64 4.16.1.3-12.amzn2023.0.2	amazonlinux 18 k
rpm-plugin-systemd-inhibit	x86_64 4.16.1.3-12.amzn2023.0.2	amazonlinux 19 k
rpm-sign-libs	x86_64 4.16.1.3-12.amzn2023.0.2	amazonlinux 22 k
slang	x86_64 2.3.2-9.amzn2023.0.1	amazonlinux 410 k
system-release	noarch 2023.0.20230210-0.amzn2023	amazonlinux 25 k
systemd	x86_64 250.8-1.amzn2023.0.1	amazonlinux 4.2 M
systemd-libs	x86_64 250.8-1.amzn2023.0.1	amazonlinux 615 k
systemd-networkd	x86_64 250.8-1.amzn2023.0.1	amazonlinux 614 k
systemd-pam	x86_64 250.8-1.amzn2023.0.1	amazonlinux 335 k
systemd-resolved	x86_64 250.8-1.amzn2023.0.1	amazonlinux 277 k
systemd-udev	x86_64 250.8-1.amzn2023.0.1	amazonlinux 1.9 M
vim-common	x86_64 2:9.0.327-1.amzn2023.0.1	amazonlinux 7.2 M
vim-data	noarch 2:9.0.327-1.amzn2023.0.1	amazonlinux 27 k
vim-enhanced	x86_64 2:9.0.327-1.amzn2023.0.1	amazonlinux 1.8 M
vim-filesystem	noarch 2:9.0.327-1.amzn2023.0.1	amazonlinux 21 k
vim-minimal	x86_64 2:9.0.327-1.amzn2023.0.1	amazonlinux 764 k
wget	x86_64 1.21.3-1.amzn2023	amazonlinux 813 k
yum	noarch 4.12.0-2.amzn2023.0.1	amazonlinux 39 k

### Transaction Summary

---

Upgrade 43 Packages

...

You can add the `--security` option to update the packages with security features only.

```
$ sudo dnf update --releasever=2023.0.20230210 --security
Amazon Linux 2023 repository                               18 MB/s | 11 MB      00:00
Last metadata expiration check: 0:00:02 ago on Mon 13 Feb 2023 10:39:32 PM UTC.
Dependencies resolved.
=====
 Package          Arch    Version           Repository      Size
 =====
Upgrading:
bind-libs          x86_64  32:9.16.27-1.amzn2023   amazonlinux    1.2 M
bind-license        noarch  32:9.16.27-1.amzn2023   amazonlinux    16 k
bind-utils          x86_64  32:9.16.27-1.amzn2023   amazonlinux    202 k
gmp                x86_64  1:6.2.1-2.amzn2023   amazonlinux    324 k
lz4-libs           x86_64  1.9.4-1.amzn2023   amazonlinux    81 k
vim-common         x86_64  2:9.0.327-1.amzn2023.0.1  amazonlinux    7.2 M
vim-data            noarch  2:9.0.327-1.amzn2023.0.1  amazonlinux    27 k
vim-enhanced       x86_64  2:9.0.327-1.amzn2023.0.1  amazonlinux    1.8 M
vim-filesystem     noarch  2:9.0.327-1.amzn2023.0.1  amazonlinux    21 k
vim-minimal         x86_64  2:9.0.327-1.amzn2023.0.1  amazonlinux    764 k
wget               x86_64  1.21.3-1.amzn2023   amazonlinux    813 k

Transaction Summary
=====
Upgrade 11 Packages
...

```

To discover AL2023 package versions, do one or more of the following:

- Run the `dnf check-update` command.
- Subscribe to the Amazon Linux repository update SNS topic (`arn:aws:sns:us-east-1:137112412989:amazon-linux-2023-ami-updates`). For more information, see [Subscribing to an Amazon SNS topic](#) in the *Amazon Simple Notification Service Developer Guide*.
- Regularly refer to the [AL2023 release notes](#).

## Important

When you apply security updates to a running instance, ensure that DNF is pointing at the latest repository version.

## Automatic service restart after (security) updates

Amazon Linux now ships with the [smart-restart](#) package. Smart-restart restarts systemd services on system updates whenever a package is installed or deleted using the systems package manager. This occurs whenever dnf (update|upgrade|downgrade) is executed.

Smart-restart uses the needs-restarting package from dnf-utils and a custom denylisting mechanism to determine which services need to be restarted and whether a system reboot is advised. If a system reboot is advised, a reboot hint marker file is generated (/run/smart-restart/reboot-hint-marker).

### To install smart-restart

Run the following DNF command (as you would with any other package).

```
$ sudo dnf install smart-restart
```

After the installation, the subsequent transactions will trigger the smart-restart logic.

### Denylist

Smart-restart can be instructed to block certain services from being restarted. The blocked services won't contribute to the decision of whether a reboot is required. To block additional services, add a file with the suffix -denylist in /etc/smart-restart-conf.d/ as shown in the following example.

```
$ cat /etc/smart-restart-conf.d/custom-denylist
# Some comments
myservice.service
```

#### Note

All \*-denylist files are read and evaluated when making the decision of whether a reboot is required.

### Custom hooks

In addition to denylisting, `smart-restart` provides a mechanism to run custom scripts before and after the attempts to restart the service. The custom scripts can be used to manually perform preparation steps or to inform other components of a remaining or completed restart.

All scripts in `/etc/smart-restart-conf.d/` with the suffix `-pre-restart` or `-post-restart` are executed. If the order is important, prefix all of the scripts with a number to ensure the execution order as shown in the following example.

```
$ ls /etc/smart-restart-conf.d/*-pre-restart
001-my-script-pre-restart
002-some-other-script-pre-restart
```

## Launching an instance with the latest repository version enabled

You can add DNF commands to a user-data script to control what RPM packages are installed on an Amazon Linux AMI when it's launched. In the following example, a user-data script is used to make sure that any instance launched with the user-data script has the same package updates installed.

```
#!/bin/bash
dnf update --releasever=2023.0.20230210
# Additional setup and install commands below
dnf install httpd php7.4 mysql80
```

You must run this script as superuser (root). To do this, run the following command.

```
$ sudo sh -c "bash nameofscript.sh"
```

For more information, see [User data and shell scripts](#) in the *Amazon EC2 User Guide*.

### Note

Instead of using a user-data script, launch the latest Amazon Linux AMI or a custom AMI that's based on the Amazon Linux AMI. The latest Amazon Linux AMI has all the necessary updates installed and is configured to point at a particular repository version.

## Getting package support information

AL2023 incorporates many different open-source software projects. Each of these projects is managed independently from Amazon Linux and have different release and end-of-support schedules. To provide you with Amazon Linux specific information about these different packages, the DNF supportinfo plugin provides metadata about a package. In the following example, the **dnf supportinfo** command returns metadata for the glibc package.

```
$ sudo dnf supportinfo --pkg glibc
Last metadata expiration check: 0:07:56 ago on Wed Mar 1 23:21:49 2023.
Name          : glibc
Version       : 2.34-52.amzn2023.0.2
State         : installed
Support Status: supported
Support Periods: from 2023-03-15      : supported
                  : from 2028-03-15      : unsupported
Support Statement: Amazon Linux 2023 End Of Life
Link          : https://aws.amazon.com/amazon-linux-ami/faqs/
Other Info    : This is the support statement for AL2023. The
...: end of life of Amazon Linux 2023 would be March 2028.
...: From this point, the Amazon Linux 2023 packages (listed
...: below) will no longer, receive any updates from AWS.
```

## Checking for newer repository versions

In an AL2023 instance, you can use the DNF utility to manage repositories and apply updated RPM packages. These packages are available in the Amazon Linux repositories. You can use the DNF command `dnf check-release-update` to check for new versions of the DNF repository.

```
$ sudo dnf check-release-update
WARNING:
A newer release of "Amazon Linux" is available.

Available Versions:

Version 2023.0.20230210:
Run the following command to update to 2023.0.20230210:

dnf update --releasever=2023.0.20230210

Release notes:
```

<https://docs.aws.amazon.com/linux/al2023/release-notes/relnotes.html>

This returns a full list of all the newer versions of the DNF repositories that are available. If nothing's returned, this means that DNF is currently configured to use the latest available version. The version of the currently installed `system-release` package sets the `releasever` DNF variable. To check the current repository version, run the following command.

```
$ rpm -q system-release --qf "%{VERSION}\n"
```

When you run DNF package transactions (such as install, update, or remove commands), a warning message notifies you of any new repository versions. For example, if you install the `httpd` package on an instance that was launched from an older version of AL2023, the following output is returned.

```
$ sudo dnf install httpd -y
Last metadata expiration check: 0:16:52 ago on Wed Mar 1 23:21:49 2023.
Dependencies resolved.
=====
Package           Arch    Version            Repository   Size
=====
Installing:
httpd            x86_64  2.4.54-3.amzn2023.0.4  amazonlinux 46 k
Installing dependencies:
apr               x86_64  1.7.2-2.amzn2023.0.2  amazonlinux 129 k
apr-util          x86_64  1.6.3-1.amzn2023.0.1  amazonlinux 98 k
generic-logos-httpd
                  noarch  18.0.0-12.amzn2023.0.3  amazonlinux 19 k
httpd-core        x86_64  2.4.54-3.amzn2023.0.4  amazonlinux 1.3 M
httpd-filesystem  noarch  2.4.54-3.amzn2023.0.4  amazonlinux 13 k
httpd-tools       x86_64  2.4.54-3.amzn2023.0.4  amazonlinux 80 k
libbrotli         x86_64  1.0.9-4.amzn2023.0.2  amazonlinux 315 k
mailcap           noarch  2.1.49-3.amzn2023.0.3  amazonlinux 33 k
Installing weak dependencies:
apr-util-openssl x86_64  1.6.3-1.amzn2023.0.1  amazonlinux 17 k
mod_http2         x86_64  1.15.24-1.amzn2023.0.3  amazonlinux 152 k
mod_lua           x86_64  2.4.54-3.amzn2023.0.4  amazonlinux 60 k
Transaction Summary
=====
Install 12 Packages

Total download size: 2.3 M
```

```
Installed size: 6.8 M
Downloading Packages:
(1/12): apr-util-openssl-1.6.3-1.am 212 kB/s | 17 kB      00:00
(2/12): apr-1.7.2-2.amzn2023.0.2.x8 1.1 MB/s | 129 kB     00:00
(3/12): httpd-core-2.4.54-3.amzn202 8.9 MB/s | 1.3 MB     00:00
(4/12): mod_http2-1.15.24-1.amzn202 1.9 MB/s | 152 kB     00:00
(5/12): apr-util-1.6.3-1.amzn2023.0 1.7 MB/s | 98 kB      00:00
(6/12): mod_lua-2.4.54-3.amzn2023.0 1.4 MB/s | 60 kB      00:00
(7/12): httpd-2.4.54-3.amzn2023.0.4 1.5 MB/s | 46 kB      00:00
(8/12): libbrotli-1.0.9-4.amzn2023. 4.4 MB/s | 315 kB     00:00
(9/12): mailcap-2.1.49-3.amzn2023.0 753 kB/s | 33 kB      00:00
(10/12): httpd-tools-2.4.54-3.amzn2 978 kB/s | 80 kB      00:00
(11/12): httpd-filesystem-2.4.54-3. 210 kB/s | 13 kB      00:00
(12/12): generic-logos-httpd-18.0.0 439 kB/s | 19 kB      00:00
-----
Total                                         6.6 MB/s | 2.3 MB   00:00

Running transaction check
Transaction check succeeded.

Running transaction test
Transaction test succeeded.

Running transaction
Preparing          :                                     1/1
Installing        : apr-1.7.2-2.amzn2023.0.2.x86_64    1/12
Installing        : apr-util-openssl-1.6.3-1.amzn2023.0.1. 2/12
Installing        : apr-util-1.6.3-1.amzn2023.0.1.x86_64 3/12
Installing        : mailcap-2.1.49-3.amzn2023.0.3.noarch 4/12
Installing        : httpd-tools-2.4.54-3.amzn2023.0.4.x86_ 5/12
Installing        : generic-logos-httpd-18.0.0-12.amzn2023 6/12
Running scriptlet: httpd-filesystem-2.4.54-3.amzn2023.0.4 7/12
Installing        : httpd-filesystem-2.4.54-3.amzn2023.0.4 7/12
Installing        : httpd-core-2.4.54-3.amzn2023.0.4.x86_6 8/12
Installing        : mod_http2-1.15.24-1.amzn2023.0.3.x86_6 9/12
Installing        : libbrotli-1.0.9-4.amzn2023.0.2.x86_64 10/12
Installing        : mod_lua-2.4.54-3.amzn2023.0.4.x86_64 11/12
Installing        : httpd-2.4.54-3.amzn2023.0.4.x86_64 12/12
Running scriptlet: httpd-2.4.54-3.amzn2023.0.4.x86_64 12/12
Verifying         : apr-1.7.2-2.amzn2023.0.2.x86_64    1/12
Verifying         : apr-util-openssl-1.6.3-1.amzn2023.0.1. 2/12
Verifying         : httpd-core-2.4.54-3.amzn2023.0.4.x86_6 3/12
Verifying         : mod_http2-1.15.24-1.amzn2023.0.3.x86_6 4/12
Verifying         : apr-util-1.6.3-1.amzn2023.0.1.x86_64 5/12
Verifying         : mod_lua-2.4.54-3.amzn2023.0.4.x86_64 6/12
Verifying         : libbrotli-1.0.9-4.amzn2023.0.2.x86_64 7/12
Verifying         : httpd-2.4.54-3.amzn2023.0.4.x86_64 8/12
```

Verifying	:	httpd-tools-2.4.54-3.amzn2023.0.4.x86_	9/12
Verifying	:	mailcap-2.1.49-3.amzn2023.0.3.noarch	10/12
Verifying	:	httpd-filesystem-2.4.54-3.amzn2023.0.4	11/12
Verifying	:	generic-logos-httpd-18.0.0-12.amzn2023	12/12

#### Installed:

apr-1.7.2-2.amzn2023.0.2.x86\_64  
apr-util-1.6.3-1.amzn2023.0.1.x86\_64  
apr-util-openssl-1.6.3-1.amzn2023.0.1.x86\_64  
generic-logos-httpd-18.0.0-12.amzn2023.0.3.noarch  
httpd-2.4.54-3.amzn2023.0.4.x86\_64  
httpd-core-2.4.54-3.amzn2023.0.4.x86\_64  
httpd-filesystem-2.4.54-3.amzn2023.0.4.noarch  
httpd-tools-2.4.54-3.amzn2023.0.4.x86\_64  
libbrotli-1.0.9-4.amzn2023.0.2.x86\_64  
mailcap-2.1.49-3.amzn2023.0.3.noarch  
mod\_http2-1.15.24-1.amzn2023.0.3.x86\_64  
mod\_lua-2.4.54-3.amzn2023.0.4.x86\_64

Complete!

## Adding, enabling, or disabling new repositories

To install a package from a different repository with the DNF package management system, add the repository information to the /etc/dnf/dnf.conf file or to its own *repository.repo* file in the /etc/yum.repos.d directory. You can do this manually. However, most DNF repositories provide their own *repository.repo* file at their repository URL.

### Note

At this time, there are no additional repositories that can be added to AL2023. This might change in the future. Also, you can write your own packages, and make those packages available to your AL2023 enterprise environment. Before you can use the packages, you must add and enable the repository where the packages are stored.

**To find out what repositories are currently enabled, you can run the following command:**

```
$ dnf repolist all --verbose
Loaded plugins: builddep, changelog, config-manager, copr, debug, debuginfo-install,
download, generate_completion_cache, groups-manager, needs-restarting, playground,
```

```
release-notification, repoclosure, repodiff, repograph, repomanage, reposync,
supportinfo
DNF version: 4.12.0
cachedir: /var/cache/dnf
Last metadata expiration check: 0:00:02 ago on Wed Mar 1 23:40:15 2023.
Repo-id : amazonlinux
Repo-name : Amazon Linux 2023 repository
Repo-status : enabled
Repo-revision : 1677203368
Repo-updated : Fri Feb 24 01:49:28 2023
Repo-pkgs : 12632
Repo-available-pkgs: 12632
Repo-size : 12 G
Repo-mirrors : https://al2023-repos-us-west-2-de612dc2.s3.dualstack.us-
west-2.amazonaws.com/core/mirrors/2023.0.20230222/x86_64/mirror.list
Repo-baseurl : https://al2023-repos-us-west-2-de612dc2.s3.dualstack.us-
west-2.amazonaws.com/core/guids/
cf9296325a6c46ff40c775a8e2d632c4c3fd9d9164014ce3304715d61b90ca8e/x86_64/
: (0 more)
Repo-expire : 172800 second(s) (last: Wed Mar 1 23:40:15
: 2023)
Repo-filename : /etc/yum.repos.d/amazonlinux.repo

Repo-id : amazonlinux-debuginfo
Repo-name : Amazon Linux 2023 repository - Debug
Repo-status : disabled
Repo-mirrors : https://al2023-repos-us-west-2-de612dc2.s3.dualstack.us-
west-2.amazonaws.com/core/mirrors/2023.0.20230222/debuginfo/x86_64/mirror.list
Repo-expire : 21600 second(s) (last: unknown)
Repo-filename : /etc/yum.repos.d/amazonlinux.repo

Repo-id : amazonlinux-source
Repo-name : Amazon Linux 2023 repository - Source packages
Repo-status : disabled
Repo-mirrors : https://al2023-repos-us-west-2-de612dc2.s3.dualstack.us-
west-2.amazonaws.com/core/mirrors/2023.0.20230222/SRPMS/mirror.list
Repo-expire : 21600 second(s) (last: unknown)
Repo-filename : /etc/yum.repos.d/amazonlinux.repo

Repo-id : kernel-livepatch
Repo-name : Amazon Linux 2023 Kernel Livepatch repository
Repo-status : disabled
Repo-mirrors : https://al2023-repos-us-west-2-de612dc2.s3.dualstack.us-
west-2.amazonaws.com/kernel-livepatch/mirrors/al2023/x86_64/mirror.list
```

```
Repo-expire      : 172800 second(s) (last: unknown)
Repo-filename    : /etc/yum.repos.d/kernel-livepatch.repo

Repo-id          : kernel-livepatch-source
Repo-name        : Amazon Linux 2023 Kernel Livepatch repository -
                  : Source packages
Repo-status      : disabled
Repo-mirrors     : https://al2023-repos-us-west-2-de612dc2.s3.dualstack.us-
west-2.amazonaws.com/kernel-livepatch/mirrors/al2023/SRPMS/mirror.list
Repo-expire      : 21600 second(s) (last: unknown)
Repo-filename    : /etc/yum.repos.d/kernel-livepatch.repo
Total packages: 12632
```

### Note

If you don't add the `--verbose` option flag, the output only includes the `Repo-id`, `Repo-name`, and `Repo-status` information.

## To add a yum repository to `/etc/yum.repos.d` directory:

1. Find the location of the `.repo` file. In this example, the `.repo` file is at <https://www.example.com/repository.repo>.
2. Add the repository with the `dnf config-manager` command.

```
$ sudo dnf config-manager --add-repo https://www.example.com/repository.repo
Loaded plugins: priorities, update-motd, upgrade-helper
adding repo from: https://www.example.com/repository.repo
grabbing file https://www.example.com/repository.repo to /etc/
yum.repos.d/repository.repo
repository.repo                                         | 4.0 kB     00:00
repo saved to /etc/yum.repos.d/repository.repo
```

After you install a repository, you must enable it as described in the next procedure.

To enable a yum repository in `/etc/yum.repos.d`, use the `dnf config-manager` command with the `--enable` flag and `repository` name.

```
$ sudo dnf config-manager --enable repository
```

**Note**

To disable a repository, use the same command syntax, but replace `--enable` with `--disable` in the command.

## Adding repositories with cloud-init

In addition to adding a repository using the previous method, you can also add a new repository using the `cloud-init` framework. Consider saving this file locally.

```
#cloud-config
yum_repos:
  repository.repo:
    baseurl: https://www.example.com/
    enabled: true
    gpgcheck: true
    gpgkey: file:///etc/pki/rpm-gpg/RPM-GPG-KEY-EXAMPLE
    name: Example Repository
```

**Note**

One advantage to using `cloud-init` is that you can add a `packages:` section to your configuration file. In this section, you can include the names of the packages that you want to install. You can install packages from either the default repository or the new repository that you added in the `cloud-config` file.

For more specific information about the structure of the YAML file, see [Adding a YUM repository](#) in the *cloud-init documentation*.

After you set up the YAML format file, you can run it in the `cloud-init` framework in the AWS CLI. Make sure to include the `--userdata` option and the name of the `.yml` file to call the desired operations.

```
$ aws ec2 run-instances \
--image-id \
```

```
resolve:ssm:/aws/service/ami-amazon-linux-latest/a12023-ami-kernel-default-x86_64 \  
--instance-type m5.xlarge \  
--region us-east-1 \  
--key-name aws-key-us-east-1 \  
--security-group-ids sg-004a7650 \  
--user-data file://cloud-config.yml
```

## Using Deterministic upgrades through versioned repository on AL2023

### Note

By default, your AL2023 instance doesn't automatically receive additional critical and important security updates at launch. Your instance initially contains the updates that were available in the version of AL2023 and the chosen AMI.

## Control the updates received from major and minor releases

With AL2023, you can ensure consistency between package versions and updates across your environment. You can also ensure consistency for multiple instances of the same Amazon Machine Image (AMI). With the deterministic upgrades through versioned repositories feature, which is turned on by default, you can apply updates based on a schedule that meets your specific needs.

Whenever we release new package updates, there's a new version to lock to, and new AMIs that lock to that version.

AL2023 locks to a specific version of your repository. This is supported for both major or minor versions. The AL2023 AMI, exposed through our SSM parameters, is always the latest version. It has the most up-to-date packages and updates, including critical and important security updates.

If you launch an instance from an existing AMI, updates aren't automatically applied. Any additional packages that are installed as part of your provisioning map to the repository version of the existing AMI.

With this feature, you're in charge of ensuring consistency among package versions and updates across your environment. This is particularly the case if you're launching multiple instances from the same AMI. You can apply updates based on a schedule that meets your needs. You can also

apply a specific set of updates on launch because these can also be locked to a specific repository version.

## Differences between minor and major version upgrades

Major version releases of AL2023 include large-scale updates and might add, delete, or update packages. To ensure compatibility, upgrade your instance to a new major version only after you test your application on that version.

Minor version releases of AL2023 include feature and security updates, but don't include package changes. This ensures that Linux features and the system library API stay available on new versions. Testing your application before updating isn't necessary.

## Control the package updates available from the AL2023 repositories

When we publish a new version of the AL2023 repositories, all previous versions are still available. By default, the plugin for managing repository versions locks to the same version that was used to build the AMI. If you want to control package updates, follow these steps.

1. Discover available repository versions by running the following command.

```
$ sudo dnf check-release-update
```

2. Select a version by running the following command.

```
$ sudo dnf --releasever=version update
```

This command starts an update using dnf from your current Amazon Linux release version to the release version that's specified in the command line. A list of the package updates is presented by dnf. Before the update is processed, you must confirm the update. After the update is complete, the new release version becomes the default release version that dnf uses for all future activities.

For more information, see [Manage package and operating system updates in AL2023](#).

## Deterministic upgrades through versioned repositories usage

### Topics

- [Using a deterministic upgraded system](#)
- [Selective update of a deterministic upgraded system](#)

- [Using persistent override with deterministic upgrade](#)

## Using a deterministic upgraded system

When you run the `dnf upgrade` command, the system checks for upgrades in the repository that the `releasever` variable specifies. A valid `releasever` is either `latest` or a date-stamped version such as `2023.5.20240624`.

You can change the value of `releasever` using one of the following methods. These methods are listed in descending system priority. This means that method 1 overrides methods 2 and 3, and method 2 overrides method 3.

1. The value in the command line flag, `--releasever=latest`, if it's used.
2. The value that's specified in the override variable file, `/etc/dnf/vars/releasever`, if it's set.
3. The currently installed version of the `system-release` package.

In the following example, the version is `2023.0.20230210`:

```
$ rpm -q system-release
system-release-2023.0.20230210-0.amzn2023.noarch
```

In a newly installed system, the override variable is not present. No upgrades are available because the system is locked to the installed version of `system-release`.

```
$ cat /etc/dnf/vars/releasever
cat: /etc/dnf/vars/releasever: No such file or directory
```

```
$ sudo dnf upgrade
Last metadata expiration check: 0:00:02 ago on Wed 15 Feb 2023 06:14:12 PM UTC.
Dependencies resolved.
Nothing to do.
Complete!
```

You can get packages of a specific version by using the `releasever` flag to provide the version that you want.

```
$ rpm -q system-release
system-release-2023.0.20230222-0.amzn2023.noarch
```

```
$ sudo dnf upgrade --releasever=2023.0.20230329
Amazon Linux 2023 repository                               26 MB/s | 12 MB      00:00
Dependencies resolved.
=====
Package          Arch    Version           Repository   Size
=====
Installing:
kernel          aarch64  6.1.21-1.45.amzn2023  amazonlinux 26 M
Upgrading:
amazon-linux-repo-s3        noarch  2023.0.20230329-0.amzn2023  amazonlinux 18 k
ca-certificates        noarch  2023.2.60-1.0.amzn2023.0.1  amazonlinux 828 k
cloud-init          noarch  22.2.2-1.amzn2023.1.7    amazonlinux 1.1 M
...
... [ list edited for clarity ]

system-release       noarch  2023.0.20230329-0.amzn2023  amazonlinux 29 k
...
... [ list edited for clarity ]

vim-data           noarch  2:9.0.1403-1.amzn2023.0.1  amazonlinux 25 k
vim-minimal        aarch64 2:9.0.1403-1.amzn2023.0.1  amazonlinux 753 k

Transaction Summary
=====
Install  1 Package
Upgrade  42 Packages

Total download size: 56 M
```

Because the `--releasever` option overrides both `system-release` and `/etc/dnf/vars/releasever`, the result of this upgrade is the following:

1. The upgrade replaces all installed packages that changed between the previous and new versions.
2. The upgrade locks the system to the repository for the new version of `system-release`.

## Selective update of a deterministic upgraded system

You might want to install selected packages from a recent release, while leaving the system locked to the original release version.

You can use `dnf check-update` to identify the packages that you want to upgrade.

```
$ sudo dnf check-update --releasever=latest --security
Amazon Linux 2023 repository                               13 MB/s | 10 MB      00:00
Last metadata expiration check: 0:00:02 ago on Wed 15 Feb 2023 02:52:21 AM UTC.

bind-libs.aarch64                                         32:9.16.27-1.amzn2023.0.1      amazonlinux
bind-license.noarch                                       32:9.16.27-1.amzn2023.0.1      amazonlinux
bind-utils.aarch64                                       32:9.16.27-1.amzn2023.0.1      amazonlinux
cryptsetup.aarch64                                         2.4.3-2.amzn2023.0.1          amazonlinux
cryptsetup-libs.aarch64                                    2.4.3-2.amzn2023.0.1          amazonlinux
curl-minimal.aarch64                                     7.85.0-1.amzn2023.0.1          amazonlinux
glibc.aarch64                                              2.34-40.amzn2023.0.2          amazonlinux
glibc-all-langpacks.aarch64                                2.34-40.amzn2023.0.2          amazonlinux
glibc-common.aarch64                                      2.34-40.amzn2023.0.2          amazonlinux
glibc-locale-source.aarch64                                2.34-40.amzn2023.0.2          amazonlinux
gmp.aarch64                                                 1:6.2.1-2.amzn2023.0.1          amazonlinux
gnupg2-minimal.aarch64                                    2.3.7-1.amzn2023.0.2          amazonlinux
gzip.aarch64                                               1.10-5.amzn2023.0.1          amazonlinux
kernel.aarch64                                             6.1.12-17.42.amzn2023          amazonlinux
kernel-tools.aarch64                                     6.1.12-17.42.amzn2023          amazonlinux
libarchive.aarch64                                         3.5.3-2.amzn2023.0.1          amazonlinux
libcurl-minimal.aarch64                                   7.85.0-1.amzn2023.0.1          amazonlinux
libsepol.aarch64                                           3.4-3.amzn2023.0.2          amazonlinux
libsolv.aarch64                                            0.7.22-1.amzn2023.0.1          amazonlinux
libxml2.aarch64                                           2.9.14-1.amzn2023.0.1          amazonlinux
logrotate.aarch64                                         3.20.1-2.amzn2023.0.2          amazonlinux
lua-libs.aarch64                                           5.4.4-3.amzn2023.0.1          amazonlinux
lz4-libs.aarch64                                           1.9.4-1.amzn2023.0.1          amazonlinux
openssl.aarch64                                           1:3.0.5-1.amzn2023.0.3          amazonlinux
openssl-libs.aarch64                                     1:3.0.5-1.amzn2023.0.3          amazonlinux
pcre2.aarch64                                              10.40-1.amzn2023.0.1          amazonlinux
pcre2-syntax.noarch                                       10.40-1.amzn2023.0.1          amazonlinux
rsync.aarch64                                              3.2.6-1.amzn2023.0.2          amazonlinux
vim-common.aarch64                                         2:9.0.475-1.amzn2023.0.1          amazonlinux
vim-data.noarch                                           2:9.0.475-1.amzn2023.0.1          amazonlinux
vim-enhanced.aarch64                                     2:9.0.475-1.amzn2023.0.1          amazonlinux
vim-filesystem.noarch                                     2:9.0.475-1.amzn2023.0.1          amazonlinux
vim-minimal.aarch64                                       2:9.0.475-1.amzn2023.0.1          amazonlinux
xz.aarch64                                                 5.2.5-9.amzn2023.0.1          amazonlinux
xz-libs.aarch64                                           5.2.5-9.amzn2023.0.1          amazonlinux
zlib.aarch64                                              1.2.11-32.amzn2023.0.3          amazonlinux
```

Install the packages that you want to upgrade. Use `sudo dnf upgrade --releasever=latest` and the package names to ensure that the `system-release` package remains unchanged.

```
$ sudo dnf upgrade --releasever=latest openssl openssl-libs
Last metadata expiration check: 0:01:28 ago on Wed 15 Feb 2023 02:52:21 AM UTC.
Dependencies resolved.
=====
 Package           Arch      Version            Repository      Size
=====
Upgrading:
openssl           aarch64   1:3.0.5-1.amzn2023.0.3    amazonlinux    1.1 M
openssl-libs       aarch64   1:3.0.5-1.amzn2023.0.3    amazonlinux    2.1 M

Transaction Summary
=====
Upgrade 2 Packages

Total download size: 3.2 M
```

### Note

Using `sudo dnf upgrade --releasever=latest` updates all packages, including `system-release`. Then, the version remains locked to the new `system-release` unless you set the persistent override.

## Using persistent override with deterministic upgrade

Instead of adding `--releasever=latest`, you can use persistent override to *unlock* the system by setting the variable value to `latest`.

```
$ echo latest | sudo tee /etc/dnf/vars/releasever
latest
```

```
$ sudo dnf upgrade
Last metadata expiration check: 0:03:36 ago on Wed 15 Feb 2023 02:52:21 AM UTC.
Dependencies resolved.
=====
 Package           Arch      Version            Repository      Size
=====
Installing:
```

kernel	aarch64 6.1.73-45.135.amzn2023	amazonlinux	24 M
<b>Upgrading:</b>			
acl	aarch64 2.3.1-2.amzn2023.0.1	amazonlinux	72 k
alternatives	aarch64 1.15-2.amzn2023.0.1	amazonlinux	36 k
amazon-ec2-net-utils	noarch 2.3.0-1.amzn2023.0.1	amazonlinux	16 k
at	aarch64 3.1.23-6.amzn2023.0.1	amazonlinux	60 k
attr	aarch64 2.5.1-3.amzn2023.0.1	amazonlinux	59 k
audit	aarch64 3.0.6-1.amzn2023.0.1	amazonlinux	249 k
audit-libs	aarch64 3.0.6-1.amzn2023.0.1	amazonlinux	116 k
aws-c-auth-libs	aarch64 0.6.5-6.amzn2023.0.2	amazonlinux	79 k
aws-c-cal-libs	aarch64 0.5.12-7.amzn2023.0.2	amazonlinux	34 k
aws-c-common-libs	aarch64 0.6.14-6.amzn2023.0.2	amazonlinux	119 k
aws-c-compression-libs	aarch64 0.2.14-5.amzn2023.0.2	amazonlinux	22 k
aws-c-event-stream-libs	aarch64 0.2.7-5.amzn2023.0.2	amazonlinux	47 k
aws-c-http-libs	aarch64 0.6.8-6.amzn2023.0.2	amazonlinux	147 k
aws-c-io-libs	aarch64 0.10.12-5.amzn2023.0.6	amazonlinux	109 k
aws-c-mqtt-libs	aarch64 0.7.8-7.amzn2023.0.2	amazonlinux	61 k
aws-c-s3-libs	aarch64 0.1.27-5.amzn2023.0.3	amazonlinux	54 k
aws-c-sdkutils-libs	aarch64 0.1.1-5.amzn2023.0.2	amazonlinux	26 k
aws-checksums-libs	aarch64 0.1.12-5.amzn2023.0.2	amazonlinux	50 k
awscli-2	noarch 2.7.8-1.amzn2023.0.4	amazonlinux	7.3 M
basesystem	noarch 11-11.amzn2023.0.1	amazonlinux	7.8 k
bash	aarch64 5.1.8-2.amzn2023.0.1	amazonlinux	1.6 M
bash-completion	noarch 1:2.11-2.amzn2023.0.1	amazonlinux	292 k
bc	aarch64 1.07.1-14.amzn2023.0.1	amazonlinux	120 k
bind-libs	aarch64 32:9.16.27-1.amzn2023.0.1	amazonlinux	1.2 M
bind-license	noarch 32:9.16.27-1.amzn2023.0.1	amazonlinux	14 k
bind-utils	aarch64 32:9.16.27-1.amzn2023.0.1	amazonlinux	206 k
binutils	aarch64 2.38-20.amzn2023.0.3	amazonlinux	4.6 M
boost-filesystem	aarch64 1.75.0-4.amzn2023.0.1	amazonlinux	55 k
boost-system	aarch64 1.75.0-4.amzn2023.0.1	amazonlinux	14 k
boost-thread	aarch64 1.75.0-4.amzn2023.0.1	amazonlinux	54 k
bzip2	aarch64 1.0.8-6.amzn2023.0.1	amazonlinux	53 k
bzip2-libs	aarch64 1.0.8-6.amzn2023.0.1	amazonlinux	44 k
c-ares	aarch64 1.17.2-1.amzn2023.0.1	amazonlinux	107 k
ca-certificates	noarch 2021.2.50-1.0.amzn2023.0.3	amazonlinux	343 k
checkpolicy	aarch64 3.4-3.amzn2023.0.1	amazonlinux	345 k
chkconfig	aarch64 1.15-2.amzn2023.0.1	amazonlinux	162 k
chrony	aarch64 4.2-7.amzn2023.0.4	amazonlinux	314 k
cloud-init	noarch 22.2.2-1.amzn2023.1.7	amazonlinux	1.1 M
cloud-utils-growpart	aarch64 0.31-8.amzn2023.0.2	amazonlinux	31 k
coreutils	aarch64 8.32-30.amzn2023.0.2	amazonlinux	1.1 M
coreutils-common	aarch64 8.32-30.amzn2023.0.2	amazonlinux	2.0 M
cpio	aarch64 2.13-10.amzn2023.0.1	amazonlinux	269 k

```
cracklib           aarch64 2.9.6-27.amzn2023.0.1      amazonlinux 83 k
cracklib-dicts    aarch64 2.9.6-27.amzn2023.0.1      amazonlinux 3.6 M
crontabs          noarch  1.11-24.20190603git.amzn2023.0.1      amazonlinux 19 k
crypto-policies    noarch  20230128-1.gitdfb10ea.amzn2023.0.1      amazonlinux 61 k
crypto-policies-scripts noarch 20230128-1.gitdfb10ea.amzn2023.0.1      amazonlinux 81 k
...
Installing dependencies:
amazon-linux-repo-cdn   noarch  2023.0.20230210-0.amzn2023      amazonlinux 16 k
xxhash-libs            aarch64 0.8.0-3.amzn2023.0.1      amazonlinux 32 k
Installing weak dependencies:
amazon-chrony-config   noarch  4.2-7.amzn2023.0.4      amazonlinux 14 k
gawk-all-langpacks     aarch64 5.1.0-3.amzn2023.0.1      amazonlinux 207 k

Transaction Summary
=====
Install  5 Packages
Upgrade 413 Packages

Total download size: 199 M
```

### Note

If you used the override variable `/etc/dnf/vars/releasever`, use the following command to restore the default locking behavior by erasing the override value.

```
$ sudo rm /etc/dnf/vars/releasever
```

## Kernel Live Patching on AL2023

You can use Kernel Live Patching for AL2023 to apply security vulnerability and critical bug patches to a running Linux kernel without rebooting or disrupting running applications. In addition, Kernel Live Patching can help improve your application's availability while also keeping your infrastructure secure and up to date.

AWS releases two types of kernel live patches for AL2023:

- **Security updates** – Include updates for Linux common vulnerabilities and exposures (CVE). These updates are typically rated as *important* or *critical* using the Amazon Linux Security Advisory ratings. They generally map to a Common Vulnerability Scoring System (CVSS) score of 7 and higher. In some cases, AWS might provide updates before a CVE is assigned. In these cases, the patches might appear as bug fixes.
- **Bug fixes** – Include fixes for critical bugs and stability issues that aren't associated with CVEs.

AWS provides kernel live patches for an AL2023 kernel version for up to 3 months after its release. After this period, you must update to a later kernel version to continue to receive kernel live patches.

AL2023 kernel live patches are made available as signed RPM packages in the existing AL2023 repositories. The patches can be installed on individual instances using existing **DNF package manager** workflows. Or, they can be installed on a group of managed instances using AWS Systems Manager.

Kernel Live Patching on AL2023 is provided at no additional cost.

## Topics

- [Limitations](#)
- [Supported configurations and prerequisites](#)
- [Work with Kernel Live Patching](#)

## Limitations

While applying a kernel live patch, you can't perform hibernation, use advanced debugging tools (such as SystemTap, kprobes, and eBPF-based tools), or access ftrace output files used by the Kernel Live Patching infrastructure.

## Supported configurations and prerequisites

Kernel Live Patching is supported on Amazon EC2 instances and on-premises virtual machines that run AL2023.

To use Kernel Live Patching on AL2023, you must use the following:

- A 64-bit x86\_64 or ARM64 architecture
- Kernel version 6.1

## Policy requirements

To download packages from AL2023 repositories, Amazon EC2 needs access to service owned Amazon S3 buckets. If you are using a Amazon Virtual Private Cloud (VPC) endpoint for Amazon S3 in your environment, ensure that your VPC endpoint policy allows access to those public buckets. The following table describes the Amazon S3 bucket that Amazon EC2 might need to access for Kernel Live Patching.

S3 bucket ARN	Description
arn:aws:s3:::al2023-repos- <i>region</i> -de612dc2/*	Amazon S3 bucket containing AL2023 repositories

## Work with Kernel Live Patching

You can enable and use Kernel Live Patching on individual instances using the command line on the instance itself. Alternatively, you can enable and use Kernel Live Patching on a group of managed instances using AWS Systems Manager.

The following sections explain how to enable and use Kernel Live Patching on individual instances using the command line.

For more information about enabling and using Kernel Live Patching on a group of managed instances, see [Use Kernel Live Patching on AL2023 instances](#) in the *AWS Systems Manager User Guide*.

### Topics

- [Enable Kernel Live Patching](#)
- [View the available kernel live patches](#)
- [Apply kernel live patches](#)
- [View the applied kernel live patches](#)
- [Disable Kernel Live Patching](#)

## Enable Kernel Live Patching

Kernel Live Patching is disabled by default on AL2023. To use live patching, you must install the **DNF** plugin for Kernel Live Patching and enable the live patching functionality.

## To enable Kernel Live Patching

- Kernel live patches are available for AL2023 with kernel version 6.1. To check your kernel version, run the following command.

```
$ sudo dnf list kernel
```

- Install the **DNF** plugin for Kernel Live Patching.

```
$ sudo dnf install -y kpatch-dnf
```

- Enable the **DNF** plugin for Kernel Live Patching.

```
$ sudo dnf kernel-livepatch -y auto
```

This command also installs the latest version of the kernel live patch RPM from the configured repositories.

- To confirm that the **DNF** plugin for kernel live patching installed successfully, run the following command.

When you enable Kernel Live Patching, an empty kernel live patch RPM is automatically applied. If Kernel Live Patching was successfully enabled, this command returns a list that includes the initial empty kernel live patch RPM.

```
$ sudo rpm -qa | grep kernel-livepatch
dnf-plugin-kernel-livepatch-1.0-0.11.amzn2023.noarch
kernel-livepatch-6.1.12-17.42-1.0-0.amzn2023.x86_64
```

- Install the **kpatch** package.

```
$ sudo dnf install -y kpatch-runtime
```

- Update the **kpatch** service if it was previously installed.

```
$ sudo dnf update kpatch-runtime
```

- Start the **kpatch** service. This service loads all of the kernel live patches upon initialization or at boot.

```
$ sudo systemctl enable kpatch.service && sudo systemctl start kpatch.service
```

## View the available kernel live patches

Amazon Linux security alerts are published to the Amazon Linux Security Center. For more information about the AL2023 security alerts, including alerts for kernel live patches, see the [Amazon Linux Security Center](#). Kernel live patches are prefixed with ALASLIVEPATCH. The Amazon Linux Security Center might not list kernel live patches that address bugs.

You can also discover the available kernel live patches for advisories and CVEs using the command line.

### To list all available kernel live patches for advisories

Use the following command.

```
$ sudo dnf updateinfo list
Last metadata expiration check: 1:06:23 ago on Mon 13 Feb 2023 09:28:19 PM UTC.
ALAS2LIVEPATCH-2021-123    important/Sec. kernel-
livepatch-6.1.12-17.42-1.0-4.amzn2023.x86_64
ALAS2LIVEPATCH-2022-124    important/Sec. kernel-
livepatch-6.1.12-17.42-1.0-3.amzn2023.x86_64
```

### To list all available kernel live patches for CVEs

Use the following command.

```
$ sudo dnf updateinfo list cves
Last metadata expiration check: 1:07:26 ago on Mon 13 Feb 2023 09:28:19 PM UTC.
CVE-2022-0123    important/Sec. kernel-livepatch-6.1.12-17.42-1.0-4.amzn2023.x86_64
CVE-2022-3210    important/Sec. kernel-livepatch-6.1.12-17.42-1.0-3.amzn2023.x86_64
```

## Apply kernel live patches

You apply kernel live patches using the **DNF** package manager in the same way that you apply regular updates. The **DNF** plugin for Kernel Live Patching manages the kernel live patches that you apply and eliminates the need to reboot.

**Tip**

We recommend that you update your kernel regularly using Kernel Live Patching to achieve that it remains secure and up to date.

You can choose to apply a specific kernel live patch, or to apply any available kernel live patches along with your regular security updates.

**To apply a specific kernel live patch**

1. Get the kernel live patch version using one of the commands described in [View the available kernel live patches](#).
2. Apply the kernel live patch for your AL2023 kernel.

```
$ sudo dnf install kernel-livepatch-kernel_version-package_version.amzn2023.x86_64
```

For example, the following command applies a kernel live patch for AL2023 kernel version 6.1.12-17.42

```
$ sudo dnf install kernel-livepatch-6.1.12-17.42-1.0-4.amzn2023.x86_64
```

**To apply any available kernel live patches along with your regular security updates**

Use the following command.

```
$ sudo dnf update --security
```

Omit the --security option to include bug fixes.

**Important**

- The kernel version isn't updated after applying kernel live patches. The version is only updated to the new version after the instance is rebooted.
- An AL2023 kernel receives kernel live patches for 3 months. After this period, no new kernel live patches are released for that kernel version.

- To continue to receive kernel live patches after 3 months, you must reboot the instance to move to the new kernel version. The instance continues to receive kernel live patches for the next 3 months after you update it.
- To check the support window for your kernel version, run the following command:

```
$ sudo dnf kernel-livepatch support
```

## View the applied kernel live patches

### To view the applied kernel live patches

Use the following command.

```
$ sudo kpatch list
Loaded patch modules:
livepatch_CVE_2022_36946 [enabled]

Installed patch modules:
livepatch_CVE_2022_36946 (6.1.57-29.131.amzn2023.x86_64)
livepatch_CVE_2022_36946 (6.1.57-30.131.amzn2023.x86_64)
```

The command returns a list of the loaded and installed security update kernel live patches. The following is example output.

#### Note

A single kernel live patch can include and install multiple live patches.

## Disable Kernel Live Patching

If you no longer need to use Kernel Live Patching, you can disable it at any time.

- Disable the use of livepatches:
  1. Disable the plugin:

```
$ sudo dnf kernel-livepatch manual
```

## 2. Disable the kpatch service:

```
$ sudo systemctl disable --now kpatch.service
```

- Fully remove the livepatch tools:

### 1. Remove the plugin:

```
$ sudo dnf remove kpatch-dnf
```

### 2. Remove kpatch-runtime:

```
$ sudo dnf remove kpatch-runtime
```

### 3. Remove any installed livepatches:

```
$ sudo dnf remove kernel-livepatch\*
```

# Getting started with programming runtimes on AL2023

AL2023 provides different versions of some language runtimes. We work with upstream projects that support multiple versions at the same time. Find information about how to install and manage these name-versioned packages using the `dnf` command to search and install these packages.

The following topics outline how each language ecosystem exists in AL2023.

## Topics

- [C, C++, and Fortran in AL2023](#)
- [Go in AL2023](#)
- [Java in AL2023](#)
- [Perl in AL2023](#)
- [PHP in AL2023](#)
- [Python in AL2023](#)
- [Rust in AL2023](#)

## C, C++, and Fortran in AL2023

AL2023 includes both the GNU Compiler Collection (GCC) and the Clang frontend for LLVM (Low Level Virtual Machine).

The major version of GCC will remain constant throughout the life time of AL2023. Minor releases bring bug fixes and might be included in AL2023 releases. Other bug, performance, and security fixes might be backported to the major version of GCC that ships in AL2023.

AL2023 includes version 11 of GCC with the C (`gcc`), C++ (`g++`), and Fortran (`gfortran`) frontends.

AL2023 does not enable the Ada (`gnat`), Go (`gcc-go`), Objective-C, or Objective-C++ frontends.

The default compiler flags that AL2023 RPMs are built with include optimization and hardening flags. To build your own code with GCC, we recommend you include optimization and hardening flags.

### Note

When `gcc --version` is invoked, a version string such as `gcc (GCC) 11.3.1 20221121 (Red Hat 11.3.1-4)` is displayed. Red Hat refers to the [GCC vendor branch](#) that the Amazon Linux GCC package is based upon. According to the bug report URL shown by `gcc --help`, all bug reports and support requests should be directed to Amazon Linux. For more information about some of the long-term changes in this vendor branch, such as the `__GNUC_RH_RELEASE__` macro, see [Fedora package sources](#).

For more information on the core toolchain, see [Core toolchain packages glibc, gcc, binutils](#).

For more information on AL2023 and its relationship to other Linux distributions, see [Relationship to Fedora](#).

For more information on the compiler triplet change in AL2023 compared to AL2, see [Compiler Triplet](#).

## Go in AL2023

You might want to build your own code written in [Go](#) on Amazon Linux, and might want to use a toolchain provided with AL2023. Similar to AL2, AL2023 will update the Go toolchain throughout the life of the operating system. This might be in response to any CVE in the toolchain we ship, or as part of a quarterly release.

Go is a relatively fast moving language. There might be a situation where existing applications written in Go have to adapt to new versions of the Go toolchain. For more information about Go, see [Go 1 and the Future of Go Programs](#).

Although AL2023 will incorporate new versions of the Go toolchain during its life, this will not be in lockstep with the upstream Go releases. Therefore, using the Go toolchain provided in AL2023 might not be suitable if you want to build Go code using cutting-edge features of the Go language and standard library.

During the lifetime of AL2023, previous package versions are not removed from the repositories. If a previous Go toolchain is required, you can choose to forgo the bug and security fixes of newer Go toolchains and install an previous version from the repositories using the same mechanisms available for any RPM.

If you want to build your own Go code on AL2023, you can use the Go toolchain included in AL2023 with the knowledge that this toolchain might move forward through the lifetime of AL2023.

## AL2023 Lambda functions written in Go

As Go compiles to native code, Lambda treats Go as a custom runtime. You can use the provided .al2023 runtime to deploy Go functions on AL2023 to Lambda.

For more information, see [Building Lambda functions with Go](#) in the *AWS Lambda Developer Guide*.

## Java in AL2023

AL2023 provides several versions of [Amazon Corretto](#) to support Java based workloads. All Java based packages included in AL2023 are built with Amazon Corretto 17.

Corretto is a build of the Open Java Development Kit (OpenJDK) with long-term support from Amazon. Corretto is certified using the Java Technical Compatibility Kit (TCK) to ensure that it meets the Java SE standard and is available on Linux, Windows, and macOS.

There is an [Amazon Corretto](#) package available for each of Corretto 1.8.0, Corretto 11, and Corretto 17.

Each Corretto version in AL2023 is supported for the same period of time as the Corretto version is, or until the end of life of AL2023, whichever is sooner. For more information, see [Amazon Linux package support statements](#) and the [Amazon Corretto FAQs](#).

## Perl in AL2023

AL2023 provides version 5.32 of the [Perl](#) programming language.

Although Perl has provided a high degree of language compatibility as part of Perl 5 releases over the past decades, Amazon Linux is not expected to move from Perl 5.32 during the AL2023 release. Amazon Linux will continue to security patch Perl for the lifetime of AL2023 in accordance with our [package support statements](#).

## Perl modules in AL2023

Various Perl modules are packaged as RPMs in AL2023. Although there are many Perl modules available as RPMs, Amazon Linux does not aim to package every possible Perl module. Modules

packaged as RPMs might be relied upon by other operating system RPM packages, so Amazon Linux will prioritize those security patches over pure feature updates.

AL2023 also includes CPAN so that Perl developers can use the idiomatic package manager for Perl modules.

## PHP in AL2023

AL2023 currently provides two versions of the [PHP](#) programming language, each supported for same period of time as upstream PHP. For more information, see [Package support statements](#).

With AL2023, you can use the new features of PHP 8.2, while still supporting applications that require PHP 8.1.

### Migrating from older PHP versions

The upstream PHP community put together [comprehensive migration documentation for moving to PHP 8.2 from PHP 8.1](#). There is also documentation for [migrating from PHP 8.0 to 8.1](#).

AL2 includes PHP 8.0, 8.1, and 8.2 in `amazon-linux-extras` enabling an easy upgrade path to AL2023.

### Migrating from PHP 7.x versions

#### Note

The [PHP](#) project maintains a list and schedule of [supported versions](#), as well as a list of [unsupported branches](#).

When AL2023 was released, all 7.x and 5.x versions of [PHP](#) were unsupported by the PHP community, and were not included as options in AL2023.

The upstream PHP community put together [comprehensive migration documentation for moving to PHP 8.0 from PHP 7.4](#). Combined with the documentation referenced in the previous section on migrating to PHP 8.1 and PHP 8.2, you can migrate your PHP based application to modern PHP.

**Note**

AL2 includes PHP 7.1, 7.2, 7.3, and 7.4 in `amazon-linux-extras`. It is important to note that all of these Extras are end-of-life and are not guaranteed to get any further security updates.

## PHP modules in AL2023

AL2023 includes many PHP modules that are included in PHP Core. AL2023 does not aim to include all of the packages in the [PHP Extension Community Library \(PECL\)](#).

## Python in AL2023

AL2023 removed Python 2.7 and any components requiring Python are now written to work with Python 3.

AL2023 makes Python 3 available as `/usr/bin/python3` to retain compatibility with customer code, as well as Python code shipped with AL2023, this will remain as Python 3.9 for the life of AL2023.

The version of python that `/usr/bin/python3` points to is considered the *system Python* and for AL2023 this is Python 3.9.

Newer versions of Python, such as Python 3.11, are made available as packages in AL2023 and are supported for the lifetime of the upstream versions. For information on how long Python 3.11 is supported, see [Python 3.11](#).

Multiple versions of Python can be installed simultaneously on AL2023. Although `/usr/bin/python3` will always be Python 3.9, each version of Python is namespaced and can be found by its version number. For example, if `python3.11` is installed, then `/usr/bin/python3.11` will exist alongside `/usr/bin/python3.9` and the `/usr/bin/python3` symlink to `/usr/bin/python3.9`.

**Note**

Do not change what the `/usr/bin/python3` symlink points to because this might break the core functionality of AL2023.

## Python modules in AL2023

Various Python modules are packaged as RPMs in AL2023. Typically, RPMs for Python modules will be built targeting only the system version of Python.

## Rust in AL2023

You might want to build your code written in [Rust](#) on Amazon Linux, and might want to use a toolchain provided with AL2023.

Similar to AL2, AL2023 will update the Rust toolchain throughout the life of the operating system. This might be in response to any CVE in the toolchain we ship, or as part of a quarterly release.

[Rust](#) is a relatively fast moving language, with new releases on approximately a six-week cadence. These releases might add new language or standard library features. Although AL2023 will incorporate new versions of the Rust toolchain during its life, this will not be in lockstep with the upstream Rust releases. Therefore, using the Rust toolchain provided in AL2023 might not be suitable if you want to build Rust code using cutting-edge features of the Rust language.

During the lifetime of AL2023, old package versions are not removed from the repositories. If an older Rust toolchain is required, you can choose to forgo bug and security fixes of newer Rust toolchains and install an older version from the repositories using the same mechanisms available for any RPM.

If you want to build your own Rust code on AL2023, you can use the Rust toolchain included in AL2023 with the knowledge that this toolchain might move forward through the lifetime of AL2023.

## AL2023 Lambda functions written in Rust

Because Rust compiles to native code, Lambda treats Rust as a custom runtime. You can use the provided .a12023 runtime to deploy Rust functions on AL2023 to Lambda.

For more information, see [Building Lambda functions with Rust](#) in the *AWS Lambda Developer Guide*.

# Security and Compliance in Amazon Linux 2023

## Important

If you want to report a vulnerability or have a security concern regarding AWS cloud services or open source projects, contact AWS Security using the [Vulnerability Reporting page](#)

Cloud security at AWS is the highest priority. As an AWS customer, you benefit from a data center and network architecture that is built to meet the requirements of the most security-sensitive organizations.

Security is a shared responsibility between AWS and you. The [shared responsibility model](#) describes this as security *of* the cloud and security *in* the cloud:

- **Security of the cloud** – AWS is responsible for protecting the infrastructure that runs AWS services in the AWS Cloud. AWS also provides you with services that you can use securely. Third-party auditors regularly test and verify the effectiveness of our security as part of the [AWS Compliance Programs](#). To learn about the compliance programs that apply to AL2023, see [AWS Services in Scope by Compliance Program](#).
- **Security in the cloud** – Your responsibility is determined by the AWS service that you use. You are also responsible for other factors including the sensitivity of your data, your company's requirements, and applicable laws and regulations.

## Topics

- [Amazon Linux Security advisories for AL2023](#)
- [Setting SELinux modes for AL2023](#)
- [Enable FIPS Mode on AL2023](#)
- [AL2023 Kernel Hardening](#)
- [UEFI Secure Boot on AL2023](#)

# Amazon Linux Security advisories for AL2023

Although we work hard to make Amazon Linux secure, at times there will be security issues that require fixing. An *advisory* is issued when a fix is available. The primary location where we publish advisories is the Amazon Linux Security Center (ALAS). For more information, see [Amazon Linux Security Center](#).

## Important

If you want to report a vulnerability or have a security concern regarding AWS cloud services or open source projects, contact AWS Security using the [Vulnerability Reporting page](#)

Information on issues and the relevant updates that affect AL2023 are published by the Amazon Linux team in several locations. It's common for security tooling to fetch information from these primary sources and present the results to you. As such, you might not directly interact with the primary sources that Amazon Linux publishes, but instead the interface provided by your preferred tooling, such as [Amazon Inspector](#).

## Amazon Linux Security Center announcements

Amazon Linux *announcements* are provided for items that do not fit into an advisory. This section contains announcements about ALAS itself, along with information that does not fit in an advisory. For more information, see [Amazon Linux Security Center \(ALAS\) Announcements](#).

For example, the [2021-001 - Amazon Linux Hotpatch Announcement for Apache Log4j](#) fit into an announcement rather than an advisory. In this announcement, Amazon Linux added a package to help customers mitigate a security issue in software that was not part of Amazon Linux.

The [Amazon Linux Security Center CVE Explorer](#) was also announced on ALAS announcements. For more information, see [New website for CVEs](#).

## Amazon Linux Security Center Frequently Asked Questions

For answers to some frequently asked questions about ALAS and how Amazon Linux evaluates CVEs, see [Amazon Linux Security Center \(ALAS\) Frequently Asked Questions \(FAQs\)](#).

# Setting SELinux modes for AL2023

By default, Security Enhanced Linux (SELinux) is enabled and set to permissive mode for AL2023. In permissive mode, permission denials are logged but not enforced. SELinux is a collection of kernel features and utilities to provide a strong, flexible, mandatory access control (MAC) architecture to the major subsystems of the kernel.

SELinux provides an enhanced mechanism to enforce the separation of information based on confidentiality and integrity requirements. This separation of information reduces threats of tampering and bypassing of application security mechanisms. It also confines damage that can be caused by malicious or flawed applications.

SELinux includes a set of sample security policy configuration files that's designed to meet everyday security goals.

For more information about SELinux features and functionality, see [SELinux Notebook](#) and [Policy Languages](#).

## Topics

- [Default SELinux status and modes for AL2023](#)
- [Change to enforcing mode](#)
- [Option to disable SELinux for AL2023](#)

## Default SELinux status and modes for AL2023

For AL2023, SELinux by default is enabled and set to permissive mode. In permissive mode, permission denials are logged but not enforced.

The **getenforce** or **sestatus** commands tell you the current SELinux status, policy, and mode.

With the default status set to enabled and permissive, the **getenforce** command returns permissive.

The **sestatus** command returns the SELinux status and the current SELinux policy as shown in the following example:

```
$ sestatus
SELinux status:          enabled
```

SELinuxfs mount:	/sys/fs/selinux
SELinux root directory:	/etc/selinux
Loaded policy name:	targeted
Current mode:	permissive
Mode from config file:	permissive
Policy MLS status:	enabled
Policy deny_unknown status:	allowed
Memory protection checking:	actual (secure)
Max kernel policy version:	33

When you run SELinux in permissive mode, users might label files incorrectly. When you run SELinux in the disabled status, files aren't labeled. Both incorrect or unlabeled files can cause problems when you change to enforcing mode.

SELinux automatically relabels files to avoid this problem. SELinux prevents labeling problems with automatic relabeling when you change the status to enabled.

## Change to enforcing mode

When you run SELinux in enforcing mode, the SELinux utility is enforcing the configured policy. SELinux governs the capabilities of select applications by allowing or denying access based on the policy's rules.

To find the current SELinux mode, run the `getenforce` command.

```
getenforce  
Permissive
```

## Edit config file to enable enforcing mode

To change the mode to enforcing, use the following steps.

1. Edit the `/etc/selinux/config` file to change to enforcing mode. The SELINUX setting should look like the following example.

```
SELINUX=enforcing
```

2. Restart your system to complete the change to enforcing mode.

```
$ sudo reboot
```

On the next boot, SELinux relabels all files and directories in the system. SELinux also adds the SELinux context for files and directories that were created when SELinux was disabled.

After changing to enforcing mode, SELinux might deny some actions because of incorrect or missing SELinux policy rules. You can view the actions that SELinux denies with the following command.

```
$ sudo ausearch -m AVC,USER_AVC,SELINUX_ERR,USER_SELINUX_ERR -ts recent
```

## Use cloud-init to enable enforcing mode

As an alternative, when you launch your instance, pass the following `cloud-config` as user-data to enable enforcing mode.

```
#cloud-config
selinux:
  mode: enforcing
```

By default, this setting causes the instance to reboot. For greater stability, we recommend rebooting your instance. However, if you prefer, you can skip the reboot by providing the following `cloud-config`.

```
#cloud-config
selinux:
  mode: enforcing
  selinux_no_reboot: 1
```

## Option to disable SELinux for AL2023

When you disable SELinux, SELinux policy isn't loaded or enforced and Access Vector Cache (AVC) messages aren't logged. You lose all benefits of running SELinux.

Instead of disabling SELinux, we recommend using permissive mode. It costs only a little more to run in permissive mode than it does to disable SELinux completely. Transitioning from permissive mode to enforcing mode requires much less of a configuration adjustment than transitioning back to enforcing mode after disabling SELinux. You can label files, and the system can track and log actions that the active policy might have denied.

## Change SELinux to permissive mode

When you run SELinux in permissive mode, SELinux policy isn't enforced. In permissive mode, SELinux logs AVC messages but doesn't deny operations. You can use these AVC messages for troubleshooting, debugging, and SELinux policy improvements.

To change SELinux to permissive mode, use the following steps.

1. Edit the `/etc/selinux/config` file to change to permissive mode. The `SELINUX` value should look like the following example.

```
SELINUX=permissive
```

2. Restart your system to complete the change to permissive mode.

```
sudo reboot
```

## Disable SELinux

When you disable SELinux, SELinux policy isn't loaded or enforced, and AVC messages aren't logged. You lose all benefits of running SELinux.

To disable SELinux, use the following steps.

1. Ensure that the `grubby` package is installed.

```
rpm -q grubby  
grubby-<version>
```

2. Configure your bootloader to add `selinux=0` to the kernel command line.

```
sudo grubby --update-kernel ALL --args selinux=0
```

3. Restart your system.

```
sudo reboot
```

4. Run the `getenforce` command to confirm that SELinux is Disabled.

```
$ getenforce
```

Disabled

For more information about SELinux, see the [SELinux Notebook](#) and [SELinux configuration](#).

## Enable FIPS Mode on AL2023

This section explains how to enable Federal Information Processing Standards (FIPS) on AL2023. For more information about FIPS, see:

- [Federal Information Processing Standard \(FIPS\)](#)
- [Compliance FAQs: Federal Information Processing Standards](#)

 **Note**

This section documents how to enable FIPS mode in AL2023, it doesn't cover the certification status of AL2023 cryptographic modules.

### Prerequisites

- An existing AL2023 (AL2023.2 or higher) Amazon EC2 instance with access to the internet to download required packages. For more information about launching an AL2023 Amazon EC2 instance, see [Launching AL2023 using the Amazon EC2 console](#).
- You must connect to your Amazon EC2 instance using SSH or AWS Systems Manager. For more information, see [Connecting to AL2023 instances](#).

 **Important**

ED25519 SSH user keys aren't supported in FIPS mode. If you launched your Amazon EC2 instance using an ED25519 SSH key pair, you must generate new keys using another algorithm (such as RSA) or you may lose access to your instance after enabling FIPS mode. For more information see [Create key pairs in the Amazon EC2 User Guide](#).

## Enable FIPS Mode

1. Connect to your AL2023 instance using SSH or AWS Systems Manager.
2. Ensure the system is up to date. For more information, see [Manage package and operating system updates in AL2023](#).
3. Ensure the crypto-policies utilities are installed and up-to-date.

```
sudo dnf -y install crypto-policies crypto-policies-scripts
```

4. Enable FIPS mode by running the following command.

```
sudo fips-mode-setup --enable
```

5. Reboot the instance using the following command.

```
sudo reboot
```

6. To verify that FIPS mode is enabled, reconnect to your instance and run the following command.

```
sudo fips-mode-setup --check
```

The following example output shows FIPS mode is enabled:

```
FIPS mode is enabled.  
Initramfs fips module is enabled.  
The current crypto policy (FIPS) is based on the FIPS policy.
```

## AL2023 Kernel Hardening

The 6.1 Linux kernel in AL2023 is configured and built with several hardening options and features.

### Kernel Hardening options (architecture independent)

<b>CONFIG option</b>	<b>AL2023/6.1/aarch64</b>	<b>AL2023/6.1/x86_64</b>
<a href="#"><u>CONFIG_ACPI_CUSTOM_METHOD</u></a>	n	n
<a href="#"><u>CONFIG_BINfmt_MISC</u></a>	m	m
<a href="#"><u>CONFIG_BUG</u></a>	y	y
<a href="#"><u>CONFIG_BUG_ON_DATA_CORRUPTION</u></a>	y	y
<a href="#"><u>CONFIG_CFI_CLANG</u></a>	N/A	N/A
<a href="#"><u>CONFIG_CFI_PERMISSIVE</u></a>	N/A	N/A
<a href="#"><u>CONFIG_COMPAT</u></a>	y	y
<a href="#"><u>CONFIG_COMPAT_BRK</u></a>	n	n
<a href="#"><u>CONFIG_COMPAT_VDSO</u></a>	N/A	n
<a href="#"><u>CONFIG_DEBUG_CREDENTIALS</u></a>	n	n
<a href="#"><u>CONFIG_DEBUG_LIST</u></a>	y	y
<a href="#"><u>CONFIG_DEBUG_NOTIFICATIONS</u></a>	n	n
<a href="#"><u>CONFIG_DEBUG_SG</u></a>	n	n
<a href="#"><u>CONFIG_DEBUG_VIRTUAL</u></a>	n	n
<a href="#"><u>CONFIG_DEBUG_WX</u></a>	n	n
<a href="#"><u>CONFIG_DEFAULT_MMAP_MIN_ADDR</u></a>	65536	65536

<b>CONFIG option</b>	<b>AL2023/6.1/aarch64</b>	<b>AL2023/6.1/x86_64</b>
<u><a href="#">CONFIG_DEVKMEM</a></u>	N/A	N/A
<u><a href="#">CONFIG_DEVMEM</a></u>	n	n
<u><a href="#">CONFIG_EFI_DISABLE_PCI_DMA</a></u>	n	n
<u><a href="#">CONFIG_FORTIFY_SOURCE</a></u>	y	y
<u><a href="#">CONFIG_HARDENED_USERCOPY</a></u>	y	y
<u><a href="#">CONFIG_HARDENED_USERCOPY_FALLBACK</a></u>	N/A	N/A
<u><a href="#">CONFIG_HARDENED_USERCOPY_PAGESPAN</a></u>	N/A	N/A
<u><a href="#">CONFIG_HIBERNATION</a></u>	y	y
<u><a href="#">CONFIG_HW_RANDOM TPM</a></u>	N/A	N/A
<u><a href="#">CONFIG_INET_DIAG</a></u>	m	m
<u><a href="#">CONFIG_INIT_ON_ALL_OCI_DEFAULT_ON</a></u>	n	n
<u><a href="#">CONFIG_INIT_ON_FREE_DEFAULT_ON</a></u>	n	n
<u><a href="#">CONFIG_INIT_STACK_ALL_ZERO</a></u>	N/A	N/A
<u><a href="#">CONFIG_IOMMU_DEFAULT_DMA_STRICT</a></u>	n	n
<u><a href="#">CONFIG_IOMMU_SUPPORT</a></u>	y	y

<b>CONFIG option</b>	<b>AL2023/6.1/aarch64</b>	<b>AL2023/6.1/x86_64</b>
<u><a href="#">CONFIG_IO_STRICT_D_EVMEM</a></u>	N/A	N/A
<u><a href="#">CONFIG_KEXEC</a></u>	y	y
<u><a href="#">CONFIG_KFENCE</a></u>	n	n
<u><a href="#">CONFIG_LDISC_AUTLOAD</a></u>	n	n
<u><a href="#">CONFIG_LEGACY_PTYS</a></u>	n	n
<u><a href="#">CONFIG_LOCK_DOWN_KERNEL_FORCE_CONFIDENTIALITY</a></u>	n	n
<u><a href="#">CONFIG_MODULES</a></u>	y	y
<u><a href="#">CONFIG_MODULE_SIG</a></u>	y	y
<u><a href="#">CONFIG_MODULE_SIG_ALL</a></u>	y	y
<u><a href="#">CONFIG_MODULE_SIG_FORCE</a></u>	n	n
<u><a href="#">CONFIG_MODULE_SIG_HASH</a></u>	sha512	sha512
<u><a href="#">CONFIG_MODULE_SIG_KEY</a></u>	certs/signing_key.pem	certs/signing_key.pem
<u><a href="#">CONFIG_MODULE_SIG_SHA512</a></u>	y	y
<u><a href="#">CONFIG_PAGE_POISONING</a></u>	n	n

<b>CONFIG option</b>	<b>AL2023/6.1/aarch64</b>	<b>AL2023/6.1/x86_64</b>
<u><a href="#">CONFIG_PAGE_POISONING_NO_SANITY</a></u>	N/A	N/A
<u><a href="#">CONFIG_PAGE_POISONING_ZERO</a></u>	N/A	N/A
<u><a href="#">CONFIG_PANIC_ON_OOPS</a></u>	y	y
<u><a href="#">CONFIG_PANIC_TIMEOUT</a></u>	0	0
<u><a href="#">CONFIG_PROC_KCORE</a></u>	y	y
<u><a href="#">CONFIG_RANDOMIZE_KSTACK_OFFSET_DEFAULT</a></u>	n	n
<u><a href="#">CONFIG_RANDOM_TRUST_BOOTLOADER</a></u>	y	y
<u><a href="#">CONFIG_RANDOM_TRUST_CPU</a></u>	y	y
<u><a href="#">CONFIG_REFCOUNT_FULL</a></u>	N/A	N/A
<u><a href="#">CONFIG_SCHED_CORE</a></u>	N/A	y
<u><a href="#">CONFIG_SCHED_STACK_END_CHECK</a></u>	y	y
<u><a href="#">CONFIG_SECCOMP</a></u>	y	y
<u><a href="#">CONFIG_SECCOMP_FILTER</a></u>	y	y
<u><a href="#">CONFIG_SECURITY</a></u>	y	y
<u><a href="#">CONFIG_SECURITY_DMESG_RESTRICT</a></u>	y	y

<b>CONFIG option</b>	<b>AL2023/6.1/aarch64</b>	<b>AL2023/6.1/x86_64</b>
<u><a href="#">CONFIG_SECURITY_LANDLOCK</a></u>	n	n
<u><a href="#">CONFIG_SECURITY_LOCKDOWN_LSM</a></u>	y	y
<u><a href="#">CONFIG_SECURITY_LOCKDOWN_LSM_EARLY</a></u>	y	y
<u><a href="#">CONFIG_SECURITY_SE_LINUX_BOOTPARAM</a></u>	y	y
<u><a href="#">CONFIG_SECURITY_SE_LINUX DEVELOP</a></u>	y	y
<u><a href="#">CONFIG_SECURITY_SE_LINUX_DISABLE</a></u>	n	n
<u><a href="#">CONFIG_SECURITY_WRITABLE_HOOKS</a></u>	N/A	N/A
<u><a href="#">CONFIG_SECURITY_YAMA</a></u>	y	y
<u><a href="#">CONFIG_SHUFFLE_PAGE_ALLOCATOR</a></u>	y	y
<u><a href="#">CONFIG_SLAB_FREELIST_HARDENED</a></u>	y	y
<u><a href="#">CONFIG_SLAB_FREELIST_RANDOM</a></u>	y	y
<u><a href="#">CONFIG_SLUB_DEBUG</a></u>	y	y
<u><a href="#">CONFIG_STACKPROTECTOR</a></u>	y	y

CONFIG option	AL2023/6.1/aarch64	AL2023/6.1/x86_64
<u><a href="#">CONFIG_STACKPROTECTOR_STRONG</a></u>	y	y
<u><a href="#">CONFIG_STATIC_USERMODEHELPER</a></u>	n	n
<u><a href="#">CONFIG_STRICT_DEVMEM</a></u>	n	n
<u><a href="#">CONFIG_STRICT_KERNEL_RWX</a></u>	y	y
<u><a href="#">CONFIG_STRICT_MODULE_RWX</a></u>	y	y
<u><a href="#">CONFIG_SYN_COOKIES</a></u>	y	y
<u><a href="#">CONFIG_VMAP_STACK</a></u>	y	y
<u><a href="#">CONFIG_WERROR</a></u>	n	n
<u><a href="#">CONFIG_ZERO_CALL_USER_REGS</a></u>	n	n

## Allow ACPI methods to be inserted/replaced at runtime ([CONFIG\\_ACPI\\_CUSTOM\\_METHOD](#))

Amazon Linux disables this option as it allows root users to write to arbitrary kernel memory.

This option is one of the [Kernel Self Protection Project Recommended Settings](#).

## Miscellaneous Binary Formats ([binfmt\\_misc](#))

Although this option is one of the [Kernel Self Protection Project \(KSPP\) Recommended Settings](#), AL2023 does not set this configuration option to what KSPP recommends. In AL2023, this feature is optional, and is built as a kernel module.

## **BUG( ) support**

This option is one of the [Kernel Self Protection Project Recommended Settings](#).

## **BUG( ) if kernel encounters data corruption in when checking kernel memory structures for validity**

Some parts of the Linux kernel will check the internal consistency of data structures and can BUG( ) when they detect data corruption.

This option is one of the [Kernel Self Protection Project Recommended Settings](#).

## **COMPAT\_BRK**

With this option disabled (which is how Amazon Linux configures the kernel), the randomize\_va\_space sysctl setting defaults to 2, which also enables heap randomization on top of mmap base, stack, and VDSO page randomization.

This option exists in the kernel to provide compatibility with some ancient libc.so.5 binaries from 1996 and earlier.

This option is one of the [Kernel Self Protection Project Recommended Settings](#).

## **COMPAT\_VDSO**

This configuration option is relevant to x86-64 and not aarch64. By setting this to n, the Amazon Linux kernel does not make a 32-bit virtual Dynamic Shared Object (VDSO) visible at a predictable address. The most recent glibc known to be broken by this option being set to n is glibc 2.3.3, from 2004.

This option is one of the [Kernel Self Protection Project Recommended Settings](#).

## **CONFIG\_DEBUG gated hardening**

Linux kernel configuration options gated by CONFIG\_DEBUG are typically designed for use in kernels built for debugging issues, and things like performance are not a priority. AL2023 enables the CONFIG\_DEBUG\_LIST hardening option.

## **Disable DMA for PCI devices in EFI stub before configuring the IOMMU**

Although this option is one of the [Kernel Self Protection Project \(KSPP\) Recommended Settings](#), AL2023 does not set this configuration option to what KSPP recommends.

## Hardening for copying memory between kernel and userspace

When the kernel needs to copy memory to or from userspace, this option enables some checks which can protect against some classes of heap overflow issues.

The CONFIG\_HARDENED\_USERCOPY\_FALLBACK option existed in kernels 4.16 through 5.15 to help kernel developers discover any missing allowlist entries via a `WARN()`. Because AL2023 ships a 6.1 kernel, this option is no longer relevant to AL2023.

The CONFIG\_HARDENED\_USERCOPY\_PAGESPAN option existed in kernels primarily as a debugging option for developers and no longer applies to the 6.1 kernel in AL2023.

This option is one of the [Kernel Self Protection Project Recommended Settings](#).

## Hibernation Support

Although this option is one of the [Kernel Self Protection Project \(KSPP\) Recommended Settings](#), AL2023 does not set this configuration option to what KSPP recommends. This option needs to be enabled in order to support the ability to [Hibernate your On-Demand Instance](#), and to support the ability to [Hibernate interrupted Spot Instances](#)

## Random Number Generation

The AL2023 kernel is configured to ensure adequate entropy is available for usage within EC2.

## CONFIG\_INET\_DIAG

Although this option is one of the [Kernel Self Protection Project \(KSPP\) Recommended Settings](#), AL2023 does not set this configuration option to what KSPP recommends. In AL2023, this feature is optional, and is built as a kernel module.

## Zero all kernel page and slab allocator memory on allocation and deallocation

Although this option is one of the [Kernel Self Protection Project \(KSPP\) Recommended Settings](#), AL2023 does not set this configuration option to what KSPP recommends. These options are disabled in AL2023 due to the possible performance impact of enabling this functionality by default. The CONFIG\_INIT\_ON\_ALLOC\_DEFAULT\_ON behavior can be enabled by adding `init_on_alloc=1` to the kernel command line, and the CONFIG\_INIT\_ON\_FREE\_DEFAULT\_ON behavior can be enabled by adding `init_on_free=1`.

## Initialize all stack variables as zero (CONFIG\_INIT\_STACK\_ALL\_ZERO)

Although this option is one of the [Kernel Self Protection Project \(KSPP\) Recommended Settings](#), AL2023 does not set this configuration option to what KSPP recommends. This option requires GCC 12 or higher, while AL2023 ships with GCC 11.

## Kernel Module Signing

AL2023 signs and validates the signatures of kernel modules. The CONFIG\_MODULE\_SIG\_FORCE option, which would require modules to have a valid signature is not enabled in order to preserve compatibility for users building third party modules. For users wanting to ensure that all kernel modules are signed, the [Lockdown Linux Security Module \(LSM\)](#) can be configured to enforce this.

## kexec

Although this option is one of the [Kernel Self Protection Project \(KSPP\) Recommended Settings](#), AL2023 does not set this configuration option to what KSPP recommends. This option is enabled so that kdump functionality can be used.

## IOMMU Support

AL2023 enables IOMMU support. The CONFIG\_IOMMU\_DEFAULT\_DMA\_STRICT option is not enabled by default, but this functionality can be configured by adding `iommu.passthrough=0 iommu.strict=1` to the kernel command line.

## kfence

Although this option is one of the [Kernel Self Protection Project \(KSPP\) Recommended Settings](#), AL2023 does not set this configuration option to what KSPP recommends.

## Legacy pty Support

AL2023 uses the modern PTY interface (devpts).

This option is one of the [Kernel Self Protection Project Recommended Settings](#).

## Lockdown Linux Security Module (LSM)

AL2023 builds the lockdown LSM, which will automatically lock down the kernel when using Secure Boot.

The CONFIG\_LOCK\_DOWN\_KERNEL\_FORCE\_CONFIDENTIALITY option is not enabled. Although this option is one of the [Kernel Self Protection Project \(KSPP\) Recommended Settings](#), AL2023 does not set this configuration option to what KSPP recommends. When not using Secure Boot, it is possible to enable the lockdown LSM and configure as wanted.

## Page Poisoning

Although this option is one of the [Kernel Self Protection Project \(KSPP\) Recommended Settings](#), AL2023 does not set this configuration option to what KSPP recommends. Similarly to [Zero all kernel page and slab allocator memory on allocation and deallocation](#), this is disabled in the AL2023 kernel due to the possible impact on performance.

## Stack Protector

The AL2023 kernel is built with the stack-protector feature of GCC enabled with the -fstack-protector-strong option.

This option is one of the [Kernel Self Protection Project Recommended Settings](#).

## seccomp BPF API

The seccomp hardening feature is used by software such as systemd and container runtimes to harden userspace applications.

This option is one of the [Kernel Self Protection Project Recommended Settings](#).

## panic() timeout

The AL2023 kernel is configured with this value set to 0, meaning that the kernel will not reboot after it panics. Although this option is one of the [Kernel Self Protection Project \(KSPP\) Recommended Settings](#), AL2023 does not set this configuration option to what KSPP recommends. This is configurable through sysctl, /proc/sys/kernel/panic, and on the kernel command line.

## Security Models

AL2023 enables SELinux in Permissive mode by default. For more information, see [Setting SELinux modes for AL2023](#).

The [Lockdown Linux Security Module \(LSM\)](#) and yama modules are also enabled.

## /proc/kcore

Although this option is one of the [Kernel Self Protection Project \(KSPP\) Recommended Settings](#), AL2023 does not set this configuration option to what KSPP recommends.

## Kernel stack offset randomization on syscall entry

Although this option is one of the [Kernel Self Protection Project \(KSPP\) Recommended Settings](#), AL2023 does not set this configuration option to what KSPP recommends. This can be enabled by setting `randomize_kstack_offset=on` on the kernel command line.

## Reference counting checks (CONFIG\_REFCOUNT\_FULL)

Although this option is one of the [Kernel Self Protection Project \(KSPP\) Recommended Settings](#), AL2023 does not set this configuration option to what KSPP recommends. This option is not currently enabled due to its possible impact on performance.

## Scheduler awareness of SMT cores (CONFIG\_SCHED\_CORE)

The AL2023 kernel is built with CONFIG\_SCHED\_CORE, which enables userspace applications to use `prctl(PR_SCHED_CORE)`. This option is one of the [Kernel Self Protection Project Recommended Settings](#).

## Check for stack corruption on calls to schedule() (CONFIG\_SCHED\_STACK\_END\_CHECK)

The AL2023 kernel is built with CONFIG\_SCHED\_STACK\_END\_CHECK enabled. This option is one of the [Kernel Self Protection Project Recommended Settings](#).

## Memory allocator hardening

The AL2023 kernel enables hardening of the kernel memory allocator with the CONFIG\_SHUFFLE\_PAGE\_ALLOCATOR, CONFIG\_SLAB\_FREELIST\_HARDENED, and CONFIG\_SLAB\_FREELIST\_RANDOM options. This option is one of the [Kernel Self Protection Project Recommended Settings](#).

## SLUB debugging support

The AL2023 kernel enables CONFIG\_SLUB\_DEBUG as this option enables optional debugging features for the allocator that can be enabled on the kernel command line. This option is one of the [Kernel Self Protection Project Recommended Settings](#).

## **CONFIG\_STATIC\_USERMODEHELPER**

Although this option is one of the [Kernel Self Protection Project \(KSPP\) Recommended Settings](#), AL2023 does not set this configuration option to what KSPP recommends. This is because CONFIG\_STATIC\_USERMODEHELPER requires special support from the distribution, which is not currently present in Amazon Linux.

### **Read-Only kernel text and rodata (CONFIG\_STRICT\_KERNEL\_RWX and CONFIG\_STRICT\_MODULE\_RWX)**

The AL2023 kernel is configured to mark kernel and kernel module text and rodata memory as read-only, and non-text memory marked as not executable. This option is one of the [Kernel Self Protection Project Recommended Settings](#).

### **TCP syncookie support (CONFIG\_SYN\_COOKIES)**

The AL2023 kernel is built with support for TCP syncookies. This option is one of the [Kernel Self Protection Project Recommended Settings](#).

### **Virtually mapped stack with guard pages (CONFIG\_VMAP\_STACK)**

The AL2023 kernel is built with CONFIG\_VMAP\_STACK, enabling virtually mapped kernel stacks with guard pages. This option is one of the [Kernel Self Protection Project Recommended Settings](#).

### **Build with compiler warnings as errors (CONFIG\_WERROR)**

Although this option is one of the [Kernel Self Protection Project \(KSPP\) Recommended Settings](#), AL2023 does not set this configuration option to what KSPP recommends.

### **Register zeroing on function exit (CONFIG\_ZERO\_CALL\_USED\_REGS)**

Although this option is one of the [Kernel Self Protection Project \(KSPP\) Recommended Settings](#), AL2023 does not set this configuration option to what KSPP recommends.

### **Minimum address for userspace allocation**

This hardening option can help reduce the impact of kernel NULL pointer bugs. This option is one of the [Kernel Self Protection Project Recommended Settings](#).

## clang specific hardening options

The AL2023 kernel is built with GCC rather than clang, so the CONFIG\_CFI\_CLANG hardening option cannot be enabled, which also makes CONFIG\_CFI\_PERMISSIVE not applicable. Although this option is one of the [Kernel Self Protection Project \(KSPP\) Recommended Settings](#), AL2023 does not set this configuration option to what KSPP recommends.

## x86-64 specific Kernel Hardening options

CONFIG option	AL2023/6.1/aarch64	AL2023/6.1/x86_64
<a href="#"><u>CONFIG_AMD_IOMMU</u></a>	N/A	y
<a href="#"><u>CONFIG_AMD_IOMMU_V2</u></a>	N/A	y
<a href="#"><u>CONFIG_IA32_EMULAT</u> <u>ION</u></a>	N/A	y
<a href="#"><u>CONFIG_INTEL_IOMMU</u></a>	N/A	y
<a href="#"><u>CONFIG_INTEL_IOMMU</u> <u>_DEFAULT_ON</u></a>	N/A	n
<a href="#"><u>CONFIG_INTEL_IOMMU</u> <u>_SVM</u></a>	N/A	n
<a href="#"><u>CONFIG_LEGACY_VSYS</u> <u>CALL_NONE</u></a>	N/A	n
<a href="#"><u>CONFIG MODIFY_LDT</u> <u>_SYSCALL</u></a>	N/A	n
<a href="#"><u>CONFIG_PAGE_TABLE</u> <u>_ISOLATION</u></a>	N/A	y
<a href="#"><u>CONFIG_RANDOMIZE_M</u> <u>EMORY</u></a>	N/A	y
<a href="#"><u>CONFIG_X86_64</u></a>	N/A	y

CONFIG option	AL2023/6.1/aarch64	AL2023/6.1/x86_64
<a href="#"><u>CONFIG_X86_MSR</u></a>	N/A	y
<a href="#"><u>CONFIG_X86_VSYSCAL_L_EMULATION</u></a>	N/A	y
<a href="#"><u>CONFIG_X86_X32</u></a>	N/A	N/A
<a href="#"><u>CONFIG_X86_X32_ABI</u></a>	N/A	n

## x86-64 Support

Base x86-64 support includes the Physical Address Extension (PAE) and no-execute (NX) bit support. This option is one of the [Kernel Self Protection Project Recommended Settings](#).

### AMD and Intel IOMMU support

The AL2023 kernel builds with support for the AMD and Intel IOMMUs. This option is one of the [Kernel Self Protection Project Recommended Settings](#).

The CONFIG\_INTEL\_IOMMU\_DEFAULT\_ON option is not set, but can be enabled by passing intel\_iommu=on to the kernel command line. Although this option is one of the [Kernel Self Protection Project \(KSPP\) Recommended Settings](#), AL2023 does not set this configuration option to what KSPP recommends.

The CONFIG\_INTEL\_IOMMU\_SVM option is not currently enabled in AL2023. Although this option is one of the [Kernel Self Protection Project \(KSPP\) Recommended Settings](#), AL2023 does not set this configuration option to what KSPP recommends.

### Support for 32bit userspace

#### Important

Support for 32bit x86 userspace is deprecated and support for running 32bit userspace binaries might be removed in a future major version of Amazon Linux.

**Note**

While AL2023 no longer includes any 32bit packages, the kernel will still support running 32bit userspace. See [32bit x86 \(i686\) Packages](#) for more information.

To support running 32bit userspace applications, AL2023 does not enable the CONFIG\_X86\_VSYSCALL\_EMULATION option, and enables the CONFIG\_IA32\_EMULATION, CONFIG\_COMPAT, and CONFIG\_X86\_VSYSCALL\_EMULATION options. Although this option is one of the [Kernel Self Protection Project \(KSPP\) Recommended Settings](#), AL2023 does not set this configuration option to what KSPP recommends.

The x32 native 32-bit ABI for 64-bit processors is not enabled (CONFIG\_X86\_X32 and CONFIG\_X86\_X32\_ABI). This option is one of the [Kernel Self Protection Project Recommended Settings](#).

## x86 Model Specific Register (MSR) support

The CONFIG\_X86\_MSR option is enabled in order to support turbostat. Although this option is one of the [Kernel Self Protection Project \(KSPP\) Recommended Settings](#), AL2023 does not set this configuration option to what KSPP recommends.

## **modify\_ldt syscall**

AL2023 does not allow user programs to modify the x86 Local Descriptor Table (LDT) with the modify\_ldt syscall. This call is required to run 16-bit or segmented code, and its absence may break software such as dosemu, running some programs under WINE, and some very old threading libraries. This option is one of the [Kernel Self Protection Project Recommended Settings](#).

## **Remove kernel mapping in user mode**

AL2023 configures the kernel so that the majority of kernel addresses are not mapped into userspace. This option is one of the [Kernel Self Protection Project Recommended Settings](#).

## **Randomize kernel memory sections**

AL2023 configures the kernel to randomize the base virtual addresses of kernel memory sections. This option is one of the [Kernel Self Protection Project Recommended Settings](#).

## **aarch64 specific Kernel Hardening options**

CONFIG option	AL2023/6.1/aarch64	AL2023/6.1/x86_64
<a href="#"><u>CONFIG_ARM64_BTI</u></a>	y	N/A
<a href="#"><u>CONFIG_ARM64_BTI_KERNEL</u></a>	N/A	N/A
<a href="#"><u>CONFIG_ARM64_PTR_AUTH</u></a>	y	N/A
<a href="#"><u>CONFIG_ARM64_PTR_AUTH_KERNEL</u></a>	y	N/A
<a href="#"><u>CONFIG_ARM64_SW_TTBR0_PAN</u></a>	y	N/A
<a href="#"><u>CONFIG_UNMAP_KERNEL_AT_EL0</u></a>	y	N/A

## Branch Target Identification

The AL2023 kernel enables support for Branch Target Identification (CONFIG\_ARM64\_BTI). This option is one of the [Kernel Self Protection Project Recommended Settings](#).

The CONFIG\_ARM64\_BTI\_KERNEL option is not enabled in AL2023 as it is built with GCC, and support for building the kernel with this option is [currently disabled in the upstream kernel](#) due to a [gcc bug](#). Although this option is one of the [Kernel Self Protection Project \(KSPP\) Recommended Settings](#), AL2023 does not set this configuration option to what KSPP recommends.

## Pointer Authentication (CONFIG\_ARM64\_PTR\_AUTH)

The AL2023 kernel is built with support for the Pointer Authentication extension (part of the ARMv8.3 Extensions), which can be used to help mitigate Return Oriented Programming (ROP) techniques. The required hardware support for pointer authentication on [Graviton](#) was introduced with Graviton 3.

The CONFIG\_ARM64\_PTR\_AUTH option is enabled and provides support for pointer authentication for userspace. Because the CONFIG\_ARM64\_PTR\_AUTH\_KERNEL option is also enabled, the AL2023 kernel is able to use the return address protection for itself.

This option is one of the [Kernel Self Protection Project Recommended Settings](#).

## Emulate Privileged Access Never using TTBR0\_EL1 switching

This option prevents the kernel from accessing userspace memory directly, with TTBR0\_EL1 being only temporarily set to a valid value by the user access routines.

This option is one of the [Kernel Self Protection Project Recommended Settings](#).

## Unmap kernel when running in userspace

The AL2023 kernel is configured to unmap the kernel when running in userspace (CONFIG\_UNMAP\_KERNEL\_AT\_EL0). This option is one of the [Kernel Self Protection Project Recommended Settings](#).

# UEFI Secure Boot on AL2023

AL2023 supports UEFI Secure Boot starting with release 2023.1. You must use AL2023 with Amazon EC2 instances that support both UEFI and UEFI Secure Boot. For more information, see [Launch an instance](#) in the *Amazon EC2 User Guide*.

AL2023 instances with UEFI Secure Boot enabled accept only kernel level code, including the Linux kernel as well as modules, that are signed by Amazon so you can ensure that your instance only runs kernel level codes signed by AWS.

For more information about Amazon EC2 instances and UEFI Secure Boot, see [UEFI Secure Boot](#) in the *Amazon EC2 User Guide*.

## Prerequisites

- You must be using an AMI with AL2023 release 2023.1 or higher.
- The instance type must support UEFI Secure Boot. For more information, see [Launch an instance](#) in the *Amazon EC2 User Guide*.

# Enable UEFI Secure Boot on AL2023

Standard AL2023 AMIs incorporate a bootloader and a kernel signed by our keys. You can enable UEFI Secure Boot either by enrolling existing instances or creating AMIs with UEFI Secure Boot pre-enabled by registering an image from a snapshot. UEFI Secure Boot isn't enabled by default on the standard AL2023 AMIs.

The boot mode of AL2023 AMIs is set to `uefi-preferred` which ensures that instances launched with these AMIs will use the UEFI firmware, if the instance type supports UEFI. If the instance type doesn't support UEFI, the instance is launched with Legacy BIOS firmware. When an instance launches in Legacy BIOS mode, UEFI Secure Boot isn't enforced.

For more information about AMI boot modes on Amazon EC2 instances, see [Boot modes](#) in the *Amazon EC2 User Guide*.

## Topics

- [Enrollment of an existing instance](#)
- [Register image from snapshot](#)
- [Revocation updates](#)
- [How UEFI Secure Boot works on AL2023](#)
- [Enrolling your own keys](#)

## Enrollment of an existing instance

To enroll an existing instance, populate the specific UEFI firmware variables with a set of keys that enable the firmware to verify the bootloader and the bootloader to verify the kernel on the next boot.

1. Amazon Linux provides a tool to simplify the enrollment process. Run the following command to provision the instance with the necessary set of keys and certificates.

```
sudo amazon-linux-sb enroll
```

2. Run the following command to reboot the instance. After the instance is rebooted, UEFI Secure Boot will be enabled.

```
sudo reboot
```

### Note

Amazon Linux AMIs currently don't support Nitro Trusted Platform Module (NitroTPM). If you need NitroTPM in addition to UEFI Secure Boot, use the information in the following section.

## Register image from snapshot

When registering an AMI from a snapshot of an Amazon EBS root volume using the Amazon EC2 `register-image` API, you can provision the AMI with a binary blob that contains the state of the UEFI variable store. By providing the AL2023 `UefiData`, you enable UEFI Secure Boot and don't need to follow the steps in the previous section.

For more information about creating and using a binary blob, see [Option B: Create a binary blob containing a pre-filled variable store](#) in the *Amazon EC2 User Guide*.

AL2023 provides a pre-built binary blob that can be used directly on Amazon EC2 instances. The binary blob is located in `/usr/share/amazon-linux-sb-keys/uefi.vars` on an running instance. This blob is provided by the `amazon-linux-sb-keys` RPM package which is installed by default on AL2023 AMIs starting with release 2023.1.

 **Note**

To ensure that you are using the latest version of keys and revocations, use the blob from the same release of AL2023 that you use to create the AMI.

When registering an image, we recommend using the `BootMode` parameter of the [RegisterImage](#) API set to `uefi`. This allows you to enable NitroTPM by setting the `TpmSupport` parameter to `v2.0`. Also, setting `BootMode` to `uefi` ensures that UEFI Secure Boot is enabled and can't be disabled by accident when switching to an instance type that doesn't support UEFI.

For more information about NitroTPM, see [NitroTPM](#) in the *Amazon EC2 User Guide*.

## Revocation updates

It may be necessary for Amazon Linux to distribute a new version of the bootloader `grub2` or the Linux kernel signed with updated keys. In that case, the old key may need to be revoked to prevent the chance of allowing exploitable bugs from previous versions of the bootloader to bypass the UEFI Secure Boot verification process.

Package updates to the `grub2` or `kernel` packages always automatically update the list of revocations into the UEFI variable store of the running instance. This means that with UEFI Secure Boot enabled, you can no longer run the old version of a package after installing a security update for the package.

## How UEFI Secure Boot works on AL2023

Unlike other Linux distributions, Amazon Linux doesn't provide an additional component, called a shim, to act as the first stage bootloader. The shim is generally signed with Microsoft keys. For example, on Linux distributions with the shim, the shim loads the grub2 bootloader which uses the shim's own code to verify the Linux kernel. Additionally, the shim maintains its own set of keys and revocations in the Machine Owner Key (MOK) database located in the UEFI variable store and controlled with the mokutil tool.

Amazon Linux doesn't provide a shim. Because the AMI owner controls the UEFI variables, this intermediary step isn't needed and would adversely affect launch and boot times. Also, we chose not to include trust to any vendor keys by default, to reduce the chance that undesired binaries could get executed. As always, customers can include binaries if they chose to do so.

With Amazon Linux, UEFI directly loads and verifies our grub2 bootloader. The grub2 bootloader was modified to use UEFI to verify the Linux kernel after loading it. Thus, the Linux Kernel is verified using the same certificates stored in the normal UEFI db variable (authorized key database) and tested against the same dbx variable (revocations database) as the bootloader and other UEFI binaries. Because we provide our own PK and KEK keys, which control access to the db database and the dbx database, we can distribute signed updates and revocations as needed without an intermediary such as the shim.

For more information about UEFI Secure Boot, see [How UEFI Secure Boot works](#) in the *Amazon EC2 User Guide*.

## Enrolling your own keys

As documented in the previous section, Amazon Linux does not require a shim for UEFI Secure Boot on Amazon EC2. When you're reading documentation for other Linux distributions, you may find documentation for managing the Machine Owner Key (MOK) database using mokutil, which is not present on AL2023. The shim and MOK environments work around some limitations of key enrollment in UEFI Firmware that aren't applicable to how Amazon EC2 implements UEFI Secure Boot. With Amazon EC2 there are mechanisms to easily directly manipulate the keys in the UEFI variable store.

If you want to enroll your own keys, you can do so either manipulate the variable store within an existing instance (see [Add keys to the variable store from within the instance](#)) or construct a binary blob that's pre-filled (see [Create a binary blob containing a pre-filled variable store](#)).